
Craft Providers

Release 1.3.0

Canonical Ltd.

Jun 01, 2022

PUBLIC APIs:

1	Executors	3
1.1	Abstract Executor	3
1.2	LXD Executor	4
1.3	Multipass Executor	8
2	Bases	13
2.1	Abstract Base	13
2.2	Build Base	15
3	craft_providers package	19
3.1	Subpackages	19
3.2	Submodules	72
3.3	Module contents	77
4	Indices and tables	81
	Python Module Index	83
	Index	85

Here you will find all of the provider documentation...

EXECUTORS

1.1 Abstract Executor

```
class craft_providers.Executor
Bases: abc.ABC
```

Interfaces to execute commands and move data in/out of an environment.

```
abstract execute_popen(command, *, cwd=None, env=None, **kwargs)
Execute a command in instance, using subprocess.Popen().
```

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (Optional[Path]) –

Return type

Popen

Returns Popen instance.

```
abstract execute_run(command, *, cwd=None, env=None, **kwargs)
Execute a command using subprocess.run().
```

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type

CompletedProcess

Returns Completed process.

Raises **subprocess.CalledProcessError** – if command fails and check is True.

abstract pull_file(*, source, destination)

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (destination.parent) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **ProviderError** – On error copying file.

Return type None

abstract push_file(*, source, destination)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (destination.parent) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **ProviderError** – On error copying file.

Return type None

abstract push_file_io(*, destination, content, file_mode, group='root', user='root')

Create or replace a file with specified content and file mode.

Parameters

- **destination** (Path) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File owner group.
- **user** (str) – File owner user.

Return type None

1.2 LXD Executor

```
class craft_providers.lxd.LXDInstance(*, name, default_command_environment=None, project='default',  
                                     remote='local', lxc=None)
```

Bases: *craft_providers.executor.Executor*

LXD Instance Lifecycle.

Parameters

- **name** (str) –
- **default_command_environment** (Optional[Dict[str, Optional[str]]]) –

- **project** (str) –
- **remote** (str) –
- **lxc** (Optional[LXC]) –

delete(*force=True*)

Delete instance.

Parameters **force** (bool) – Delete even if running.

Raises [LXDError](#) – On unexpected error.

Return type None

execute_popen(*command*, *, *cwd=None*, *env=None*, ***kwargs*)

Execute a command in instance, using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

execute_run(*command*, *, *cwd=None*, *env=None*, ***kwargs*)

Execute a command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises [subprocess.CalledProcessError](#) – if command fails and check is True.

exists()

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises [LXDError](#) – On unexpected error.

is_mounted(**host_source*, *target*)

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (PurePath) – Instance path to check.

Return type bool**Returns** True if host_source is mounted at target.**Raises** [LXDError](#) – On unexpected error.**is_running()**

Check if instance is running.

Return type bool**Returns** True if instance is running.**Raises** [LXDError](#) – On unexpected error.**launch(*, image, image_remote, map_user_uid=False, ephemeral=False, uid=None)**

Launch instance.

Parameters

- **image** (str) – Image name to launch.
- **image_remote** (str) – Image remote name.
- **map_user_id** – Whether id mapping should be used.
- **uid** (Optional[int]) – If **map_user_id** is True, the host user ID to map to instance root.
- **ephemeral** (bool) – Flag to enable ephemeral instance.
- **map_user_uid** (bool) –

Raises [LXDError](#) – On unexpected error.**Return type** None**mount(*, host_source, target, device_name=None)**

Mount host source directory to target mount point.

Checks first to see if already mounted. If no device name is given, it will be generated with the format “disk-{target.as_posix()}”.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (PurePath) – Instance path to mount to.
- **device_name** (Optional[str]) – Name for disk device.

Raises [LXDError](#) – On unexpected error.**Return type** None**pull_file(*, source, destination)**

Copy a file from the environment to host.

Parameters

- **source** (PurePath) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (destination.parent) must exist.

Raises

- **FileNotFoundException** – If source file or destination’s parent directory does not exist.
- **LXDError** – On unexpected error copying file.

Return type None**push_file**(**, source, destination*)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (PurePath) – Target environment file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination’s parent directory does not exist.
- **LXDError** – On unexpected error copying file.

Return type None**push_file_io**(**, destination, content, file_mode, group='root', user='root'*)

Create or replace file with content and file mode.

Parameters

- **destination** (PurePath) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Raises **LXDError** – On unexpected error.**Return type** None**start()**

Start instance.

Raises **LXDError** – on unexpected error.**Return type** None**stop()**

Stop instance.

Raises **LXDError** – on unexpected error.**Return type** None**supports_mount()**

Check if instance supports mounting from host.

Return type bool**Returns** True if mount is supported.**unmount**(*target*)

Unmount mount target shared with host.

Parameters `target` (Path) – Target shared with host to unmount.

Raises `LXDError` – On failure to unmount target.

Return type None

`unmount_all()`

Unmount all mounts shared with host.

Raises `LXDError` – On failure to unmount target.

Return type None

1.3 Multipass Executor

```
class craft_providers.multipass.MultipassInstance(*, name, multipass=None)
Bases: craft_providers.executor.Executor
```

Multipass Instance Lifecycle.

Parameters

- `name` (str) – Name of multipass instance.
- `multipass` (Optional[Multipass]) –

`delete()`

Delete instance and purge.

Return type None

`execute_popen(command, *, cwd=None, env=None, **kwargs)`

Execute process in instance using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- `command` (List[str]) – Command to execute.
- `env` (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- `kwargs` – Additional keyword arguments for subprocess.Popen().
- `cwd` (Optional[Path]) –

Return type Popen

Returns Popen instance.

`execute_run(command, *, cwd=None, env=None, **kwargs)`

Execute command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- `command` (List[str]) – Command to execute.
- `env` (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- `kwargs` – Keyword args to pass to subprocess.run().
- `cwd` (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises `subprocess.CalledProcessError` – if command fails and check is True.

exists()

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises `MultipassError` – On unexpected failure.

is_mounted(*, host_source, target)

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (Path) – Instance path to check.

Return type bool

Returns True if host_source is mounted at target.

Raises `MultipassError` – On unexpected failure.

is_running()

Check if instance is running.

Return type bool

Returns True if instance is running.

Raises `MultipassError` – On unexpected failure.

launch(*, image, cpus=2, disk_gb=256, mem_gb=2)

Launch instance.

Parameters

- **image** (str) – Name of image to create the instance with.
- **instance_cpus** – Number of CPUs.
- **instance_disk_gb** – Disk allocation in gigabytes.
- **instance_mem_gb** – Memory allocation in gigabytes.
- **instance_name** – Name of instance to use/create.
- **instance_stop_time_mins** – Stop time delay in minutes.
- **cpus** (int) –
- **disk_gb** (int) –
- **mem_gb** (int) –

Raises `MultipassError` – On unexpected failure.

Return type None

mount(*, host_source, target)

Mount host host_source directory to target mount point.

Checks first to see if already mounted.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (Path) – Instance path to mount to.

Raises [MultipassError](#) – On unexpected failure.

Return type None

pull_file(**, source, destination*)

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- [FileNotFoundException](#) – If source file or destination's parent directory does not exist.
- [MultipassError](#) – On unexpected error copying file.

Return type None

push_file(**, source, destination*)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- [FileNotFoundException](#) – If source file or destination's parent directory does not exist.
- [MultipassError](#) – On unexpected error copying file.

Return type None

push_file_io(**, destination, content, file_mode, group='root', user='root'*)

Create or replace file with content and file mode.

Multipass transfers data as “ubuntu” user, forcing us to first copy a file to a temporary location before moving to a (possibly) root-owned location and with appropriate permissions.

Parameters

- **destination** (Path) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Return type None

start()

Start instance.

Raises `MultipassError` – On unexpected failure.

Return type None

stop(*, `delay_mins=0`)

Stop instance.

Parameters `delay_mins` (int) – Delay shutdown for specified minutes.

Raises `MultipassError` – On unexpected failure.

Return type None

umount(*target*)

Unmount mount target shared with host.

Parameters `target` (Path) – Target shared with host to umount.

Raises `MultipassError` – On failure to umount target.

Return type None

umount_all()

Unmount all mounts shared with host.

Raises `MultipassError` – On failure to umount target.

Return type None

2.1 Abstract Base

```
class craft_providers.Base  
Bases: abc.ABC
```

Interface for providers to configure instantiated environments.

Defines how to setup/configure an environment that has been instantiated by a provider and prepare it for some operation, e.g. execute build. It must account for:

- (1) the OS type and version.
- (2) the provided image that was launched, e.g. bootstrapping a minimal image versus a more fully featured one.
- (3) any dependencies that are required for the operation to complete, e.g. installed applications, networking configuration, etc. This includes any environment configuration that the application will assume is available.

Variables compatibility_tag – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: compatibility_tag = f'{appname}-{Base.compatibility_tag}.{apprevision}' to ensure base compatibility levels are maintained.

abstract get_command_environment()

Get command environment to use when executing commands.

Return type Dict[str, Optional[str]]

Returns Dictionary of environment, allowing None as a value to indicate that a value should be unset.

abstract setup(*, executor, retry_wait=0.25, timeout=None)

Prepare base instance for use by the application.

Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

Setup should not be called more than once in a given instance to refresh/update the environment, use *warmup* for that.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).

- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None**abstract** `wait_until_ready(*, executor, retry_wait=0.25, timeout=None)`

Wait until base instance is ready.

Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running setup(), e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None**abstract** `warmup(*, executor, retry_wait=0.25, timeout=None)`

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

2.2 Buildd Base

```
class craft_providers.bases.BuilddBase(*, alias, environment=None, hostname='craft-buildd-instance')
```

Bases: `craft_providers.base.Base`

Support for Ubuntu minimal buildd images.

Variables

- **compatibility_tag** – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: `compatibility_tag = f'{appname}-{BuildBase.compatibility_tag}.{apprevision}'` to ensure base compatibility levels are maintained.
- **instance_config_path** – Path to persistent environment configuration used for compatibility checks (or other data). Set to `/etc/craft-instance.conf`, but may be overridden for application-specific reasons.
- **instance_config_class** – Class defining instance configuration. May be overridden with an application-specific subclass of `InstanceConfiguration` to enable application-specific extensions.

Parameters

- **alias** (`BuilddBaseAlias`) – Base alias / version.
- **environment** (`Optional[Dict[str, Optional[str]]]`) – Environment to set in `/etc/environment`.
- **hostname** (`str`) – Hostname to configure.

`get_command_environment()`

Get command environment to use when executing commands.

Return type `Dict[str, Optional[str]]`

Returns Dictionary of environment, allowing `None` as a value to indicate that a value should be unset.

`instance_config_class`

alias of `craft_providers.bases.instance_config.InstanceConfiguration`

`setup(*, executor, retry_wait=0.25, timeout=None)`

Prepare base instance for use by the application.

Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

Setup may be called more than once in a given instance to refresh/update the environment.

If timeout is specified, abort operation if time has been exceeded.

Guarantees provided by this setup:

- configured `/etc/environment`
- configured hostname
- networking available (IP & DNS resolution)
- apt cache up-to-date

- snapd configured and ready
- system services are started and ready

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type

None

`wait_until_ready(*, executor, retry_wait=0.25, timeout=None)`

Wait until base instance is ready.

Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running setup(), e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

If timeout is specified, abort operation if time has been exceeded.

Guarantees provided by this wait:

- networking available (IP & DNS resolution)
- system services are started and ready

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

ProviderError – on timeout or unexpected error.

Return type

None

`warmup(*, executor, retry_wait=0.25, timeout=None)`

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

Guarantees provided by this wait:

- OS and instance config are compatible
- networking available (IP & DNS resolution)
- system services are started and ready

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).

- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- *BaseCompatibilityError* – if instance is incompatible.
- *BaseConfigurationError* – on other unexpected error.

Return type None

CRAFT_PROVIDERS PACKAGE

3.1 Subpackages

3.1.1 craft_providers.actions package

Submodules

craft_providers.actions.snap_installer module

Helpers for snap commands.

exception `craft_providers.actions.snap_installer.SnapInstallationError`(*brief*: str, *details*: Optional[str] = None, *resolution*: Optional[str] = None)

Bases: `craft_providers.errors.ProviderError`

Unexpected error during snap installation.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

`craft_providers.actions.snap_installer.inject_from_host`(**executor*, *snap_name*, *classic*)

Inject snap from host snap.

Raises `SnapInstallationError` – on unexpected error.

Parameters

- **executor** (`Executor`) –
- **snap_name** (str) –
- **classic** (bool) –

Return type None

`craft_providers.actions.snap_installer.install_from_store`(**executor*, *snap_name*, *channel*, *classic*)

Install snap from store into target.

Perform installation using method which prevents refreshing.

Parameters

- **executor** (*Executor*) – Executor for target.
- **snap_name** (str) – Name of snap to install.
- **channel** (str) – Channel to install from.
- **classic** (bool) – Install in classic mode.

Raises *SnapInstallationError* – on unexpected error.

Return type None

Module contents

Executor helpers package.

3.1.2 craft_providers.bases package

Submodules

craft_providers.bases.buildd module

Buildd image(s).

```
class craft_providers.bases.buildd.BuilddBase(*, alias, environment=None,
                                              hostname='craft-buildd-instance')
```

Bases: *craft_providers.base.Base*

Support for Ubuntu minimal buildd images.

Variables

- **compatibility_tag** – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: `compatibility_tag = f'{appname}-{BuildBase.compatibility_tag}.{apprevision}'` to ensure base compatibility levels are maintained.
- **instance_config_path** – Path to persistent environment configuration used for compatibility checks (or other data). Set to `/etc/craft-instance.conf`, but may be overridden for application-specific reasons.
- **instance_config_class** – Class defining instance configuration. May be overridden with an application-specific subclass of `InstanceConfiguration` to enable application-specific extensions.

Parameters

- **alias** (*BuilddBaseAlias*) – Base alias / version.
- **environment** (Optional[Dict[str, Optional[str]]]) – Environment to set in `/etc/environment`.
- **hostname** (str) – Hostname to configure.

alias: *craft_providers.bases.buildd.BuilddBaseAlias*

```
compatibility_tag: str = 'buildd-base-v0'

get_command_environment()
    Get command environment to use when executing commands.

    Return type Dict[str, Optional[str]]

    Returns Dictionary of environment, allowing None as a value to indicate that a value should be unset.

instance_config_class
    alias of craft\_providers.bases.instance\_config.InstanceConfiguration

instance_config_path: pathlib.Path = PosixPath('/etc/craft-instance.conf')

setup(*, executor, retry_wait=0.25, timeout=None)
    Prepare base instance for use by the application.

    Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

    Setup may be called more than once in a given instance to refresh/update the environment.

    If timeout is specified, abort operation if time has been exceeded.

    Guarantees provided by this setup:
        • configured /etc/environment
        • configured hostname
        • networking available (IP & DNS resolution)
        • apt cache up-to-date
        • snapd configured and ready
        • system services are started and ready

Parameters
    • executor (Executor) – Executor for target container.
    • retry_wait (float) – Duration to sleep() between status checks (if required).
    • timeout (Optional[float]) – Timeout in seconds.

Raises
    • BaseCompatibilityError – if instance is incompatible.
    • BaseConfigurationError – on other unexpected error.

Return type None

wait_until_ready(*, executor, retry_wait=0.25, timeout=None)
    Wait until base instance is ready.

    Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running setup(), e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

    If timeout is specified, abort operation if time has been exceeded.

    Guarantees provided by this wait:
```

- networking available (IP & DNS resolution)
- system services are started and ready

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises *ProviderError* – on timeout or unexpected error.

Return type None

warmup(**, executor, retry_wait=0.25, timeout=None*)

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

Guarantees provided by this wait:

- OS and instance config are compatible
- networking available (IP & DNS resolution)
- system services are started and ready

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- *BaseCompatibilityError* – if instance is incompatible.
- *BaseConfigurationError* – on other unexpected error.

Return type None

class *craft_providers.bases.build.BuilddBaseAlias*(*value*)

Bases: *enum.Enum*

Mappings for supported buildd images.

BIONIC = '18.04'

FOCAL = '20.04'

JAMMY = '22.04'

XENIAL = '16.04'

craft_providers.bases.build.default_command_environment()

Provide default command environment dictionary.

The minimum environment for the buildd image to be configured and function properly. This contains the default environment found in Ubuntu's /etc/environment, replaced with the "secure_path" defaults used by sudo for instantiating PATH. In practice it really just means the PATH set by sudo.

Default /etc/environment found in supported Ubuntu versions: PATH=/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:/sbin:/bin:/usr/games:/usr/local/games

Default /etc/sudoers secure_path found in supported Ubuntu versions:
 PATH=/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:/sbin:/bin:/snap/bin

Return type Dict[str, Optional[str]]

Returns Dictionary of environment key/values.

craft_providers.bases.errors module

Base errors.

exception craft_providers.bases.errors.BaseCompatibilityError(*reason*, *, *details*=None)

Bases: *craft_providers.errors.ProviderError*

Base configuration compatibility error.

Parameters

- **reason** (str) – Reason for incompatibility.
- **details** (Optional[str]) –

brief: str

exception craft_providers.bases.errors.BaseConfigurationError(*brief*: str, *details*: Optional[str] = None, *resolution*: Optional[str] = None)

Bases: *craft_providers.errors.ProviderError*

Error configuring the base.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

craft_providers.bases.instance_config module

Persistent instance config / datastore resident in provided environment.

class craft_providers.bases.instance_config.InstanceConfiguration(***data*)

Bases: pydantic.main.BaseModel

Instance configuration datastore.

Parameters

- **compatibility_tag** – Compatibility tag for instance.
- **snaps** – dictionary of snaps and their revisions, e.g. snaps:
 - snapcraft**: revision: “x100”
 - charmcraft**: revision: 834
- **data** (Any) –

compatibility_tag: Optional[str]

classmethod `load(executor, config_path=PosixPath('/etc/craft-instance.conf'))`

Load an instance config file from an environment.

Parameters

- **executor** (`Executor`) – Executor for instance.
- **config_path** (`Path`) – Path to configuration file. Default is `/etc/craft-instance.conf`.

Return type `Optional[InstanceConfiguration]`

Returns The `InstanceConfiguration` object or `None` if the config does not exist or is empty.

Raises `BaseConfigurationError` – If the file cannot be loaded from the environment.

marshal()

Create a dictionary containing the `InstanceConfiguration` data.

Return type `Dict[str, Any]`

Returns The newly created dictionary.

save(executor, config_path=PosixPath('/etc/craft-instance.conf'))

Save an instance config file to an environment.

Parameters

- **executor** (`Executor`) – Executor for instance.
- **config_path** (`Path`) – Path to configuration file. Default is `/etc/craft-instance.conf`.

Return type `None`

smaps: Optional[Dict[str, Dict[str, Any]]]

classmethod unmarshal(data)

Create and populate a new `InstanceConfig` object from dictionary data.

The unmarshal method validates the data in the dictionary and populates the corresponding fields in the `InstanceConfig` object.

Parameters `data (Dict[str, Any])` – The dictionary data to unmarshal.

Return type `InstanceConfiguration`

Returns The newly created `InstanceConfiguration` object.

Raises `BaseConfigurationError` – If validation fails.

classmethod update(executor, data, config_path=PosixPath('/etc/craft-instance.conf'))

Update an instance config file in an environment.

New values are added and existing values are updated. No data are removed. If there is no existing config to update, then a new config is created.

Parameters

- **executor** (`Executor`) – Executor for instance.
- **data** (`Dict[str, Any]`) – The dictionary to update instance with.
- **config_path** (`Path`) –

Return type `InstanceConfiguration`

Returns The updated `InstanceConfiguration` object.

`craft_providers.bases.instance_config.update_nested_dictionaries(config_data, new_data)`

Recursively update a dictionary containing nested dictionaries.

New values are added and existing values are updated. No data are removed.

Parameters

- **config_data** (Dict[str, Any]) – dictionary of config data to update.
- **new_data** (Dict[str, Any]) – data to update *config_data* with.

Return type Dict[str, Any]

Module contents

Collection of bases used to configure build environments.

exception `craft_providers.bases.BaseCompatibilityError(reason, *, details=None)`

Bases: `craft_providers.errors.ProviderError`

Base configuration compatibility error.

Parameters

- **reason** (str) – Reason for incompatibility.
- **details** (Optional[str]) –

brief: str

exception `craft_providers.bases.BaseConfigurationError(brief: str, details: Optional[str] = None, resolution: Optional[str] = None)`

Bases: `craft_providers.errors.ProviderError`

Error configuring the base.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

class `craft_providers.bases.BuilddBase(*, alias, environment=None, hostname='craft-buildd-instance')`

Bases: `craft_providers.base.Base`

Support for Ubuntu minimal buildd images.

Variables

- **compatibility_tag** – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: `compatibility_tag = f'{appname}-{BuildBase.compatibility_tag}.{apprevision}'` to ensure base compatibility levels are maintained.
- **instance_config_path** – Path to persistent environment configuration used for compatibility checks (or other data). Set to `/etc/craft-instance.conf`, but may be overridden for application-specific reasons.

- **instance_config_class** – Class defining instance configuration. May be overridden with an application-specific subclass of InstanceConfiguration to enable application-specific extensions.

Parameters

- **alias** (*BuildBaseAlias*) – Base alias / version.
- **environment** (Optional[Dict[str, Optional[str]]]) – Environment to set in /etc/environment.
- **hostname** (str) – Hostname to configure.

compatibility_tag: str = 'buildd-base-v0'

get_command_environment()

Get command environment to use when executing commands.

Return type Dict[str, Optional[str]]

Returns Dictionary of environment, allowing None as a value to indicate that a value should be unset.

instance_config_class

alias of *craft_providers.bases.instance_config.InstanceConfiguration*

instance_config_path: pathlib.Path = PosixPath('/etc/craft-instance.conf')

setup(*, executor, retry_wait=0.25, timeout=None)

Prepare base instance for use by the application.

Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

Setup may be called more than once in a given instance to refresh/update the environment.

If timeout is specified, abort operation if time has been exceeded.

Guarantees provided by this setup:

- configured /etc/environment
- configured hostname
- networking available (IP & DNS resolution)
- apt cache up-to-date
- snapd configured and ready
- system services are started and ready

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

`wait_until_ready(*, executor, retry_wait=0.25, timeout=None)`

Wait until base instance is ready.

Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running setup(), e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

If timeout is specified, abort operation if time has been exceeded.

Guarantees provided by this wait:

- networking available (IP & DNS resolution)
- system services are started and ready

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (*float*) – Duration to sleep() between status checks (if required).
- **timeout** (*Optional[float]*) – Timeout in seconds.

Raises *ProviderError* – on timeout or unexpected error.

Return type None

`warmup(*, executor, retry_wait=0.25, timeout=None)`

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

Guarantees provided by this wait:

- OS and instance config are compatible
- networking available (IP & DNS resolution)
- system services are started and ready

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (*float*) – Duration to sleep() between status checks (if required).
- **timeout** (*Optional[float]*) – Timeout in seconds.

Raises

- *BaseCompatibilityError* – if instance is incompatible.
- *BaseConfigurationError* – on other unexpected error.

Return type None

`class craft_providers.bases.BuilddBaseAlias(value)`

Bases: `enum.Enum`

Mappings for supported buildd images.

BIONIC = '18.04'

FOCAL = '20.04'

JAMMY = '22.04'

```
XENIAL = '16.04'
```

3.1.3 craft_providers.lxd package

Submodules

craft_providers.lxd.errors module

LXD Errors.

```
exception craft_providers.lxd.errors.LXDError(brief: str, details: Optional[str] = None, resolution: Optional[str] = None)
```

Bases: *craft_providers.errors.ProviderError*

Unexpected LXD error.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

```
exception craft_providers.lxd.errors.LXDInstallationError(reason, *, details=None)
```

Bases: *craft_providers.lxd.errors.LXDError*

LXD Installation Error.

Parameters

- **reason** (str) – Reason for install failure.
- **details** (Optional[str]) – Optional details to include.

brief: str

craft_providers.lxd.installer module

LXD Provider.

```
craft_providers.lxd.installer.ensure_lxd_is_ready(*, remote='local',
                                                 lxc=<craft_providers.lxd.lxc.LXC object>,
                                                 lxd=<craft_providers.lxd.lxd.LXD object>)
```

Ensure LXD is ready for use.

Raises *LXDError* – on error.

Parameters

- **remote** (str) –
- **lxc** (*LXC*) –
- **lxd** (*LXD*) –

Return type None

```
craft_providers.lxd.installer.install(sudo=True)
```

Install LXD.

Install application, using sudo if specified.

Return type str

Returns LXD version.

Raises

- [LXDInstallationError](#) – on installation error.
- [LXDError](#) – on unexpected error.

Parameters sudo (bool) –

```
craft_providers.lxd.installer.is_initialized(*, remote, lxc)
```

Verify that LXD has been initialized and configuration looks valid.

If LXD has been installed but the user has not initialized it (lxd init), the default profile won't have devices configured. Trying to launch an instance or create a project using this profile will result in failures.

Return type bool

Returns True if initialized, else False.

Parameters

- remote (str) –
- lxc ([LXC](#)) –

```
craft_providers.lxd.installer.is_installed()
```

Check if LXD is installed (and found on PATH).

Return type bool

Returns True if lxd is installed.

```
craft_providers.lxd.installer.is_user_permitted()
```

Check if user has permissions to connect to LXD.

Return type bool

Returns True if user has correct permissions.

craft_providers.lxd.launcher module

LXD Instance Provider.

```
craft_providers.lxd.launcher.launch(name, *, base_configuration, image_name, image_remote,
                                    auto_clean=False, auto_create_project=False, ephemeral=False,
                                    map_user_uid=False, uid=None, use_snapshots=False,
                                    project='default', remote='local', lxc=<craft_providers.lxd.lxc.LXC
                                    object>)
```

Create, start, and configure instance.

If auto_clean is enabled, automatically delete an existing instance that is deemed to be incompatible, rebuilding it with the specified environment.

Parameters

- name (str) – Name of instance.

- **base_configuration** ([Base](#)) – Base configuration to apply to instance.
- **image_name** (str) – LXD image to use, e.g. “20.04”.
- **image_remote** (str) – LXD image to use, e.g. “ubuntu”.
- **auto_clean** (bool) – Automatically clean instance, if incompatible.
- **auto_create_project** (bool) – Automatically create LXD project, if needed.
- **ephemeral** (bool) – Create ephemeral instance.
- **map_user_uid** (bool) – Map host uid/gid to instance’s root uid/gid.
- **uid** (Optional[int]) – The uid to be mapped, if `map_user_id` is enabled.
- **use_snapshots** (bool) – Use LXD snapshots for bootstrapping images.
- **project** (str) – LXD project to create instance in.
- **remote** (str) – LXD remote to create instance on.
- **lxc** ([LXC](#)) – LXC client.

Return type [LXDInstance](#)

Returns LXD instance.

Raises

- [BaseConfigurationError](#) – on unexpected error configuration base.
- [LXDError](#) – on unexpected LXD error.

[craft_providers.lxd.lxc module](#)

LXC wrapper.

```
class craft_providers.lxd.lxc.LXC(*, lxc_path=PosixPath('lxc'))  
    Bases: object  
  
Wrapper for lxc command-line interface.  
  
    Parameters lxc_path (Path) –  
  
    config_device_add_disk(*, instance_name, source, path, device, project='default', remote='local')  
        Mount host source directory to target mount point.
```

Parameters

- **instance_name** (str) – Name of instance.
- **source** (Path) – Host path.
- **path** (PurePath) – Mount target in instance.
- **device** (str) – Name of device.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises [LXDError](#) – on unexpected error.

Return type None

```
config_device_remove(*, instance_name, device, project='default', remote='local')  
    Mount host source directory to target mount point.
```

Parameters

- **instance_name** (str) – Name of instance.
- **device** (str) – Name of device.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

config_device_show(*, *instance_name*, *project='default'*, *remote='local'*)

Show full device configuration.

Parameters

- **instance_name** (str) – Name of instance.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type Dict[str, Any]

config_set(*, *instance_name*, *key*, *value*, *project='default'*, *remote='local'*)

Set *instance_name* configuration key.

Parameters

- **instance_name** (str) – Name of instance.
- **key** (str) – Config key name.
- **value** (str) – Config key value.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

delete(*, *instance_name*, *force=False*, *project='default'*, *remote='local'*)

Delete *instance_name*.

Parameters

- **instance_name** (str) – Name of instance.
- **force** (bool) – Force deletion if running.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

exec(*, *command*, *instance_name*, *cwd=None*, *mode=None*, *project='default'*, *remote='local'*,
runner=<function run>, ***kwargs*)

Execute command in *instance_name* with specified runner.

Parameters

- **command** (List[str]) – Command to execute in the instance.
- **instance_name** (str) – Name of instance to execute in.
- **cwd** (Optional[str]) – Optional current working directory for command.
- **mode** (Optional[str]) – Override terminal mode Valid options include: “auto”, “interactive”, “non-interactive”. lxd default is “auto”.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.
- **runner** (Callable) – Execution function to invoke, e.g. subprocess.run or Popen. First argument is finalized command with the attached kwargs.
- **kwargs** – Additional kwargs for runner.

Returns Runner’s instance.

file_pull(**, instance_name, source, destination, create_dirs=False, recursive=False, project='default', remote='local')*

Retrieve file from *instance_name*.

Parameters

- **instance_name** (str) – Name of instance.
- **source** (PurePath) – Path in environment to pull.
- **destination** (Path) – Path in host to write to.
- **create_dirs** (bool) – Create any directories necessary.
- **recursive** (bool) – Recursively transfer files.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises *LXDError* – on unexpected error.

Return type None

file_push(**, instance_name, source, destination, create_dirs=False, recursive=False, gid=None, uid=None, mode=None, project='default', remote='local')*

Create file with content and file mode.

Parameters

- **instance_name** (str) – Name of instance to push file to.
- **source** (Path) – Path in host to push.
- **destination** (PurePath) – Path in environment to write to.
- **create_dirs** (bool) – Create any directories necessary.
- **recursive** (bool) – Recursively transfer files.
- **gid** (Optional[int]) – Optional gid to set on push (lxd’s default is -1).
- **uid** (Optional[int]) – Optional uid to set on push (lxd’s default is -1).
- **mode** (Optional[str]) – Optional file mode to set on file.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

`has_image(image_name, *, project='default', remote='local')`

Check if image with given alias name is present.

Parameters

- `image_name` – Name of image alias.
- `project` (str) – Name of LXD project.
- `remote` (str) – Name of LXD remote.

Return type bool

`image_copy(*, image, image_remote, alias=None, project='default', remote='local')`

Copy image.

Parameters

- `instance_name` – Optional instance name.
- `alias` (Optional[str]) – New alias to add to image.
- `image` (str) – Image to copy.
- `project` (str) – Name of LXD project.
- `remote` (str) – Name of LXD remote.
- `image_remote` (str) –

Raises `LXDError` – on unexpected error.

Return type None

`image_delete(*, image, project='default', remote='local')`

Delete image.

Parameters

- `image` (str) – Image to delete.
- `project` (str) – Name of LXD project.
- `remote` (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

`image_list(*, project='default', remote='local')`

List images.

Parameters

- `project` (str) – Name of LXD project.
- `remote` (str) – Name of LXD remote.

Return type List[Dict[str, Any]]

`info(*, instance_name=None, project='default', remote='local')`

Show instance or server information.

Parameters

- `instance_name` (Optional[str]) – Optional instance name.

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type Dict[str, Any]

launch(**, instance_name*, *image*, *image_remote*, *config_keys=None*, *ephemeral=False*, *project='default'*, *remote='local'*)

Launch instance.

Parameters

- **instance_name** (str) – Name of instance to launch.
- **image** (str) – Name of image to use.
- **image_remote** (str) – Name of image's remote.
- **config_keys** (Optional[Dict[str, str]]) – Configuration keys to set.
- **ephemeral** (bool) – Use ephemeral instance.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

list(**, project='default'*, *remote='local'*)

List instances and their status.

Parameters

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Return type List[Dict[str, Any]]

Returns List of containers and their info.

Raises `LXDError` – on unexpected error.

list_names(**, project='default'*, *remote='local'*)

List container names.

A helper to get a list of container names from list().

Parameters

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Return type List[str]

Returns List of container names.

Raises `LXDError` – on unexpected error.

profile_edit(**, profile*, *config*, *project='default'*, *remote='local'*)

Set profile configuration.

Parameters

- **profile** (str) – Name of profile.

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.
- **config** (Dict[str, Any]) –

Raises `LXDError` – on unexpected error.

Return type None

profile_show(*, *profile*, *project*=‘default’, *remote*=‘local’)
Get profile configuration.

Parameters

- **profile** (str) – Name of profile.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type Dict[str, Any]

project_create(*, *project*, *remote*=‘local’)
Create project.

Parameters

- **project** (str) – Name of LXD project to create.
- **remote** (str) – Name of LXD remote to create project on.

Raises `LXDError` – on unexpected error.

Return type None

project_delete(*, *project*, *remote*=‘local’)
Delete project, if it exists.

Parameters

- **project** (str) – Name of LXD project to delete.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

project_list(*remote*=‘local’)
Get list of projects.

Parameters **remote** (str) – Name of LXD remote to query.

Return type List[str]

Returns List of project names.

Raises `LXDError` – on unexpected error.

publish(*, *instance_name*, *alias*=None, *force*=False, *image_remote*=‘local’, *project*=‘default’, *remote*=‘local’)

Publish image from instance.

Parameters

- **instance_name** (str) – Name of instance to publish image from.

- **alias** (Optional[str]) – New alias to define at target.
- **force** (bool) – Force publishing of image, even if container is running.
- **image_remote** (str) – Name of remote to publish image to.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote instance is found on.

Raises `LXDError` – on unexpected error.

Return type None

remote_add(*, remote, addr, protocol='simplestreams')

Add a public remote.

Parameters

- **remote** (str) – Name of remote to add.
- **addr** (str) – Address of remote.
- **protocol** (str) – Name of protocol (“simplestreams” or “lxd”).

Raises `LXDError` – on unexpected error.

Return type None

remote_list()

Get list of remotes.

Return type Dict[str, Any]

Returns dictionary with remote name mapping to config.

start(*, instance_name, project='default', remote='local')

Start container.

Parameters

- **instance_name** (str) – Name of instance to start.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

stop(*, instance_name, force=False, timeout=-1, project='default', remote='local')

Stop container.

Parameters

- **instance_name** (str) – Name of instance to stop.
- **force** (bool) – Force instance to stop.
- **timeout** (int) – Timeout in seconds. -1 is no timeout.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

craft_providers.lxd.lxc.load_yaml(*data*)

Load yaml without additional resolvers.

LXD may return YAML that has datetimes that are not valid when parsed to `datetime.datetime()`. Instead just use the base loader and avoid resolving this type (and others).

craft_providers.lxd.lxd module

LXD command-line interface helpers.

class craft_providers.lxd.lxd.LXD(*, lxd_path=PosixPath('lxd'))

Bases: `object`

Interface to `lxd` command-line.

Parameters `lxd_path` (`Path`) – Path to lxd.

Variables `minimum_required_version` – Minimum lxd version required for compatibility.

init(*, auto=False, sudo=False)

Initialize LXD.

Sudo is required if user is not in lxd group.

Parameters

- `auto` (`bool`) – Use default settings.
- `sudo` (`bool`) – Use sudo to invoke init.

Return type `None`**is_supported_version()**

Check if LXD version is supported.

A helper to check if LXD meets minimum supported version for craft-providers (currently ≥ 4.0).

Return type `bool`

Returns True if installed version is supported.

minimum_required_version = '4.0'**version()**

Query LXD version.

The version is of the format: <major>.<minor>[.<micro>]

Version examples: - 4.13 - 4.0.5 - 2.0.12

Return type `str`

Returns Version string.

wait_ready(*, sudo=False, timeout=None)

Wait until LXD is ready.

Sudo is required if user is not in lxd group.

Parameters

- `sudo` (`bool`) – Use sudo to invoke waitready.
- `timeout` (`Optional[int]`) – Timeout in seconds.

Return type `None`

craft_providers.lxd.lxd_instance module

LXD Instance Executor.

```
class craft_providers.lxd.lxd_instance.LXDInstance(*, name, default_command_environment=None,
                                                 project='default', remote='local', lxc=None)
```

Bases: *craft_providers.executor.Executor*

LXD Instance Lifecycle.

Parameters

- **name** (str) –
- **default_command_environment** (Optional[Dict[str, Optional[str]]]) –
- **project** (str) –
- **remote** (str) –
- **lxc** (Optional[LXC]) –

```
delete(force=True)
```

Delete instance.

Parameters **force** (bool) – Delete even if running.

Raises **LXDError** – On unexpected error.

Return type None

```
execute_popen(command, *, cwd=None, env=None, **kwargs)
```

Execute a command in instance, using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

```
execute_run(command, *, cwd=None, env=None, **kwargs)
```

Execute a command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises `subprocess.CalledProcessError` – if command fails and check is True.

`exists()`

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises `LXDError` – On unexpected error.

`is_mounted(*, host_source, target)`

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (PurePath) – Instance path to check.

Return type bool

Returns True if host_source is mounted at target.

Raises `LXDError` – On unexpected error.

`is_running()`

Check if instance is running.

Return type bool

Returns True if instance is running.

Raises `LXDError` – On unexpected error.

`launch(*, image, image_remote, map_user_uid=False, ephemeral=False, uid=None)`

Launch instance.

Parameters

- **image** (str) – Image name to launch.
- **image_remote** (str) – Image remote name.
- **map_user_id** – Whether id mapping should be used.
- **uid** (Optional[int]) – If `map_user_id` is True, the host user ID to map to instance root.
- **ephemeral** (bool) – Flag to enable ephemeral instance.
- **map_user_uid** (bool) –

Raises `LXDError` – On unexpected error.

Return type None

`mount(*, host_source, target, device_name=None)`

Mount host source directory to target mount point.

Checks first to see if already mounted. If no device name is given, it will be generated with the format “disk-{target.as_posix()}”.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (PurePath) – Instance path to mount to.

- **device_name** (Optional[str]) – Name for disk device.

Raises [LXDError](#) – On unexpected error.

Return type None

pull_file(*, source, destination)

Copy a file from the environment to host.

Parameters

- **source** (PurePath) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (destination.parent) must exist.

Raises

- [FileNotFoundException](#) – If source file or destination's parent directory does not exist.
- [LXDError](#) – On unexpected error copying file.

Return type None

push_file(*, source, destination)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (PurePath) – Target environment file path to copy to. Parent directory (destination.parent) must exist.

Raises

- [FileNotFoundException](#) – If source file or destination's parent directory does not exist.
- [LXDError](#) – On unexpected error copying file.

Return type None

push_file_io(*, destination, content, file_mode, group='root', user='root')

Create or replace file with content and file mode.

Parameters

- **destination** (PurePath) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Raises [LXDError](#) – On unexpected error.

Return type None

start()

Start instance.

Raises [LXDError](#) – on unexpected error.

Return type None

stop()

Stop instance.

Raises `LXDError` – on unexpected error.

Return type None

supports_mount()

Check if instance supports mounting from host.

Return type bool

Returns True if mount is supported.

umount(*target*)

Unmount mount target shared with host.

Parameters `target` (Path) – Target shared with host to umount.

Raises `LXDError` – On failure to umount target.

Return type None

umount_all()

Unmount all mounts shared with host.

Raises `LXDError` – On failure to umount target.

Return type None

craft_providers.lxd.project module

Project helper utilities.

`craft_providers.lxd.project.create_with_default_profile(*, lxc, project, profile='default', profile_project='default', remote='local')`

Create a project with a valid default profile.

LXD does not set a valid profile on newly created projects. This will create a project and set the profile to match the specified profile, typically the default.

Parameters

- `project` (str) – Name of project to create.
- `remote` (str) – Name of remote.
- `profile_name` – Name of profile to copy.
- `lxc` ([LXC](#)) –
- `profile` (str) –
- `profile_project` (str) –

Raises `LXDError` – on unexpected error.

Return type None

`craft_providers.lxd.project.purge(*, lxc, project, remote='local')`

Purge a project including its instances and images.

The lxc command does not provide a straight-forward option to purge a project. This helper will purge anything related to a specified one.

Parameters

- **project** (str) – Name of project to delete.
- **remote** (str) – Name of remote.
- **lxc** ([LXC](#)) –

Raises [LXDError](#) – on unexpected error.

Return type None

craft_providers.lxd.remotes module

Remote helper utilities.

`craft_providers.lxd.remotes.configure_buildd_image_remote(lxc=<craft_providers.lxd.lxc.LXC object>)`

Configure buildd remote, adding remote as required.

Parameters **lxc** ([LXC](#)) – LXC client.

Return type str

Returns Name of remote to pass to launcher.

Module contents

LXD environment provider.

`class craft_providers.lxd.LXC(*, lxc_path=PosixPath('lxc'))`

Bases: object

Wrapper for lxc command-line interface.

Parameters **lxc_path** (Path) –

`config_device_add_disk(*, instance_name, source, path, device, project='default', remote='local')`

Mount host source directory to target mount point.

Parameters

- **instance_name** (str) – Name of instance.
- **source** (Path) – Host path.
- **path** (PurePath) – Mount target in instance.
- **device** (str) – Name of device.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises [LXDError](#) – on unexpected error.

Return type None

`config_device_remove(*, instance_name, device, project='default', remote='local')`

Mount host source directory to target mount point.

Parameters

- **instance_name** (str) – Name of instance.
- **device** (str) – Name of device.

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

config_device_show(*, *instance_name*, *project='default'*, *remote='local'*)

Show full device configuration.

Parameters

- **instance_name** (str) – Name of instance.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type Dict[str, Any]

config_set(*, *instance_name*, *key*, *value*, *project='default'*, *remote='local'*)

Set *instance_name* configuration key.

Parameters

- **instance_name** (str) – Name of instance.
- **key** (str) – Config key name.
- **value** (str) – Config key value.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

delete(*, *instance_name*, *force=False*, *project='default'*, *remote='local'*)

Delete *instance_name*.

Parameters

- **instance_name** (str) – Name of instance.
- **force** (bool) – Force deletion if running.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

exec(*, *command*, *instance_name*, *cwd=None*, *mode=None*, *project='default'*, *remote='local'*,
runner=<function run>, ***kwargs*)

Execute command in *instance_name* with specified runner.

Parameters

- **command** (List[str]) – Command to execute in the instance.
- **instance_name** (str) – Name of instance to execute in.
- **cwd** (Optional[str]) – Optional current working directory for command.

- **mode** (Optional[str]) – Override terminal mode. Valid options include: “auto”, “interactive”, “non-interactive”. lxd default is “auto”.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.
- **runner** (Callable) – Execution function to invoke, e.g. subprocess.run or Popen. First argument is finalized command with the attached kwargs.
- **kwarg**s – Additional kwargs for runner.

Returns Runner’s instance.

file_pull(**instance_name*, *source*, *destination*, *create_dirs=False*, *recursive=False*, *project='default'*, *remote='local'*)

Retrieve file from *instance_name*.

Parameters

- **instance_name** (str) – Name of instance.
- **source** (PurePath) – Path in environment to pull.
- **destination** (Path) – Path in host to write to.
- **create_dirs** (bool) – Create any directories necessary.
- **recursive** (bool) – Recursively transfer files.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises [LXDError](#) – on unexpected error.

Return type None

file_push(**instance_name*, *source*, *destination*, *create_dirs=False*, *recursive=False*, *gid=None*, *uid=None*, *mode=None*, *project='default'*, *remote='local'*)

Create file with content and file mode.

Parameters

- **instance_name** (str) – Name of instance to push file to.
- **source** (Path) – Path in host to push.
- **destination** (PurePath) – Path in environment to write to.
- **create_dirs** (bool) – Create any directories necessary.
- **recursive** (bool) – Recursively transfer files.
- **gid** (Optional[int]) – Optional gid to set on push (lxd’s default is -1).
- **uid** (Optional[int]) – Optional uid to set on push (lxd’s default is -1).
- **mode** (Optional[str]) – Optional file mode to set on file.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises [LXDError](#) – on unexpected error.

Return type None

has_image(*image_name*, *, *project*='default', *remote*='local')

Check if image with given alias name is present.

Parameters

- **image_name** – Name of image alias.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Return type bool**image_copy**(*, *image*, *image_remote*, *alias*=None, *project*='default', *remote*='local')

Copy image.

Parameters

- **instance_name** – Optional instance name.
- **alias** (Optional[str]) – New alias to add to image.
- **image** (str) – Image to copy.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.
- **image_remote** (str) –

Raises `LXDError` – on unexpected error.

Return type None**image_delete**(*, *image*, *project*='default', *remote*='local')

Delete image.

Parameters

- **image** (str) – Image to delete.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None**image_list**(*, *project*='default', *remote*='local')

List images.

Parameters

- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Return type List[Dict[str, Any]]**info**(*, *instance_name*=None, *project*='default', *remote*='local')

Show instance or server information.

Parameters

- **instance_name** (Optional[str]) – Optional instance name.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type `Dict[str, Any]`

`launch(*, instance_name, image, image_remote, config_keys=None, ephemeral=False, project='default', remote='local')`

Launch instance.

Parameters

- **instance_name** (`str`) – Name of instance to launch.
- **image** (`str`) – Name of image to use.
- **image_remote** (`str`) – Name of image’s remote.
- **config_keys** (`Optional[Dict[str, str]]`) – Configuration keys to set.
- **ephemeral** (`bool`) – Use ephemeral instance.
- **project** (`str`) – Name of LXD project.
- **remote** (`str`) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type `None`

`list(*, project='default', remote='local')`

List instances and their status.

Parameters

- **project** (`str`) – Name of LXD project.
- **remote** (`str`) – Name of LXD remote.

Return type `List[Dict[str, Any]]`

Returns List of containers and their info.

Raises `LXDError` – on unexpected error.

`list_names(*, project='default', remote='local')`

List container names.

A helper to get a list of container names from list().

Parameters

- **project** (`str`) – Name of LXD project.
- **remote** (`str`) – Name of LXD remote.

Return type `List[str]`

Returns List of container names.

Raises `LXDError` – on unexpected error.

`profile_edit(*, profile, config, project='default', remote='local')`

Set profile configuration.

Parameters

- **profile** (`str`) – Name of profile.
- **project** (`str`) – Name of LXD project.
- **remote** (`str`) – Name of LXD remote.

- **config** (Dict[str, Any]) –

Raises `LXDError` – on unexpected error.

Return type None

profile_show(*, *profile*, *project*=`'default'`, *remote*=`'local'`)

Get profile configuration.

Parameters

- **profile** (str) – Name of profile.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type Dict[str, Any]

project_create(*, *project*, *remote*=`'local'`)

Create project.

Parameters

- **project** (str) – Name of LXD project to create.
- **remote** (str) – Name of LXD remote to create project on.

Raises `LXDError` – on unexpected error.

Return type None

project_delete(*, *project*, *remote*=`'local'`)

Delete project, if it exists.

Parameters

- **project** (str) – Name of LXD project to delete.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

project_list(*remote*=`'local'`)

Get list of projects.

Parameters **remote** (str) – Name of LXD remote to query.

Return type List[str]

Returns List of project names.

Raises `LXDError` – on unexpected error.

publish(*, *instance_name*, *alias*=`None`, *force*=`False`, *image_remote*=`'local'`, *project*=`'default'`, *remote*=`'local'`)

Publish image from instance.

Parameters

- **instance_name** (str) – Name of instance to publish image from.
- **alias** (Optional[str]) – New alias to define at target.
- **force** (bool) – Force publishing of image, even if container is running.

- **image_remote** (str) – Name of remote to publish image to.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote instance is found on.

Raises `LXDError` – on unexpected error.

Return type None

remote_add(*, remote, addr, protocol='simplestreams')

Add a public remote.

Parameters

- **remote** (str) – Name of remote to add.
- **addr** (str) – Address of remote.
- **protocol** (str) – Name of protocol (“simplestreams” or “lxd”).

Raises `LXDError` – on unexpected error.

Return type None

remote_list()

Get list of remotes.

Return type Dict[str, Any]

Returns dictionary with remote name mapping to config.

start(*, instance_name, project='default', remote='local')

Start container.

Parameters

- **instance_name** (str) – Name of instance to start.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

stop(*, instance_name, force=False, timeout=-1, project='default', remote='local')

Stop container.

Parameters

- **instance_name** (str) – Name of instance to stop.
- **force** (bool) – Force instance to stop.
- **timeout** (int) – Timeout in seconds. -1 is no timeout.
- **project** (str) – Name of LXD project.
- **remote** (str) – Name of LXD remote.

Raises `LXDError` – on unexpected error.

Return type None

class craft_providers.lxd.LXD(*, lxd_path=PosixPath('lxd'))

Bases: object

Interface to *lxd* command-line.

Parameters `lxd_path` (Path) – Path to lxd.

Variables `minimum_required_version` – Minimum lxd version required for compatibility.

init(*, `auto=False`, `sudo=False`)

Initialize LXD.

Sudo is required if user is not in lxd group.

Parameters

- `auto` (bool) – Use default settings.
- `sudo` (bool) – Use sudo to invoke init.

Return type

None

is_supported_version()

Check if LXD version is supported.

A helper to check if LXD meets minimum supported version for craft-providers (currently >= 4.0).

Return type

bool

Returns True if installed version is supported.

minimum_required_version = '4.0'

version()

Query LXD version.

The version is of the format: <major>.<minor>[.<micro>]

Version examples: - 4.13 - 4.0.5 - 2.0.12

Return type

str

Returns Version string.

wait_ready(*, `sudo=False`, `timeout=None`)

Wait until LXD is ready.

Sudo is required if user is not in lxd group.

Parameters

- `sudo` (bool) – Use sudo to invoke waitready.
- `timeout` (Optional[int]) – Timeout in seconds.

Return type

None

exception `craft_providers.lxd.LXDError`(*brief: str, details: Optional[str] = None, resolution: Optional[str] = None*)

Bases: `craft_providers.errors.ProviderError`

Unexpected LXD error.

Parameters

- `brief` (str) –
- `details` (Optional[str]) –
- `resolution` (Optional[str]) –

brief: str

```
exception craft_providers.lxd.LXDInstallationError(reason, *, details=None)
Bases: craft_providers.lxd.errors.LXDError
```

LXD Installation Error.

Parameters

- **reason** (str) – Reason for install failure.
- **details** (Optional[str]) – Optional details to include.

brief: str

```
class craft_providers.lxd.LXDInstance(*, name, default_command_environment=None, project='default',
                                         remote='local', lxc=None)
```

Bases: craft_providers.executor.Executor

LXD Instance Lifecycle.

Parameters

- **name** (str) –
- **default_command_environment** (Optional[Dict[str, Optional[str]]]) –
- **project** (str) –
- **remote** (str) –
- **lxc** (Optional[LXC]) –

delete(force=True)

Delete instance.

Parameters **force** (bool) – Delete even if running.

Raises LXDError – On unexpected error.

Return type None

execute_popen(command, *, cwd=None, env=None, **kwargs)

Execute a command in instance, using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

execute_run(command, *, cwd=None, env=None, **kwargs)

Execute a command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.

- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises subprocess.CalledProcessError – if command fails and check is True.

exists()

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises LXDError – On unexpected error.

is_mounted(*, host_source, target)

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (PurePath) – Instance path to check.

Return type bool

Returns True if host_source is mounted at target.

Raises LXDError – On unexpected error.

is_running()

Check if instance is running.

Return type bool

Returns True if instance is running.

Raises LXDError – On unexpected error.

launch(*, image, image_remote, map_user_uid=False, ephemeral=False, uid=None)

Launch instance.

Parameters

- **image** (str) – Image name to launch.
- **image_remote** (str) – Image remote name.
- **map_user_id** – Whether id mapping should be used.
- **uid** (Optional[int]) – If map_user_id is True, the host user ID to map to instance root.
- **ephemeral** (bool) – Flag to enable ephemeral instance.
- **map_user_uid** (bool) –

Raises LXDError – On unexpected error.

Return type None

mount(*, host_source, target, device_name=None)

Mount host source directory to target mount point.

Checks first to see if already mounted. If no device name is given, it will be generated with the format “disk-{target.as_posix()}”.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (PurePath) – Instance path to mount to.
- **device_name** (Optional[str]) – Name for disk device.

Raises [LXDError](#) – On unexpected error.

Return type None

pull_file(*, source, destination)

Copy a file from the environment to host.

Parameters

- **source** (PurePath) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (destination.parent) must exist.

Raises

- **FileNotFoundException** – If source file or destination’s parent directory does not exist.
- [LXDError](#) – On unexpected error copying file.

Return type None

push_file(*, source, destination)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (PurePath) – Target environment file path to copy to. Parent directory (destination.parent) must exist.

Raises

- **FileNotFoundException** – If source file or destination’s parent directory does not exist.
- [LXDError](#) – On unexpected error copying file.

Return type None

push_file_io(*, destination, content, file_mode, group='root', user='root')

Create or replace file with content and file mode.

Parameters

- **destination** (PurePath) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Raises [LXDError](#) – On unexpected error.

Return type None

start()

Start instance.

Raises `LXDError` – on unexpected error.

Return type None

stop()

Stop instance.

Raises `LXDError` – on unexpected error.

Return type None

supports_mount()

Check if instance supports mounting from host.

Return type bool

Returns True if mount is supported.

umount(*target*)

Unmount mount target shared with host.

Parameters `target` (Path) – Target shared with host to umount.

Raises `LXDError` – On failure to umount target.

Return type None

umount_all()

Unmount all mounts shared with host.

Raises `LXDError` – On failure to umount target.

Return type None

craft_providers.lxd.configure_build_image_remote(*lxc*=<craft_providers.lxd.lxc.LXC object>)

Configure build remote, adding remote as required.

Parameters `lxc` (`LXC`) – LXC client.

Return type str

Returns Name of remote to pass to launcher.

craft_providers.lxd.ensure_lxd_is_ready(*, *remote*='local', *lxc*=<craft_providers.lxd.lxc.LXC object>, *lxd*=<craft_providers.lxd.lxd.LXD object>)

Ensure LXD is ready for use.

Raises `LXDError` – on error.

Parameters

- `remote` (str) –
- `lxc` (`LXC`) –
- `lxd` (`LXD`) –

Return type None

craft_providers.lxd.install(*sudo*=True)

Install LXD.

Install application, using sudo if specified.

Return type str

Returns LXD version.

Raises

- [LXDInstallationError](#) – on installation error.
- [LXDError](#) – on unexpected error.

Parameters `sudo` (bool) –

`craft_providers.lxd.is_initialized(*, remote, lxc)`

Verify that LXD has been initialized and configuration looks valid.

If LXD has been installed but the user has not initialized it (lxd init), the default profile won't have devices configured. Trying to launch an instance or create a project using this profile will result in failures.

Return type bool

Returns True if initialized, else False.

Parameters

- `remote` (str) –
- `lxc` ([LXC](#)) –

`craft_providers.lxd.is_installed()`

Check if LXD is installed (and found on PATH).

Return type bool

Returns True if lxd is installed.

`craft_providers.lxd.is_user_permitted()`

Check if user has permissions to connect to LXD.

Return type bool

Returns True if user has correct permissions.

`craft_providers.lxd.launch(name, *, base_configuration, image_name, image_remote, auto_clean=False, auto_create_project=False, ephemeral=False, map_user_uid=False, uid=None, use_snapshots=False, project='default', remote='local', lxc=<craft_providers.lxd.lxc.LXC object>)`

Create, start, and configure instance.

If `auto_clean` is enabled, automatically delete an existing instance that is deemed to be incompatible, rebuilding it with the specified environment.

Parameters

- `name` (str) – Name of instance.
- `base_configuration` ([Base](#)) – Base configuration to apply to instance.
- `image_name` (str) – LXD image to use, e.g. “20.04”.
- `image_remote` (str) – LXD image to use, e.g. “ubuntu”.
- `auto_clean` (bool) – Automatically clean instance, if incompatible.
- `auto_create_project` (bool) – Automatically create LXD project, if needed.
- `ephemeral` (bool) – Create ephemeral instance.
- `map_user_uid` (bool) – Map host uid/gid to instance's root uid/gid.
- `uid` (Optional[int]) – The uid to be mapped, if `map_user_id` is enabled.

- **use_snapshots** (bool) – Use LXD snapshots for bootstrapping images.
- **project** (str) – LXD project to create instance in.
- **remote** (str) – LXD remote to create instance on.
- **lxc** (*LXC*) – LXC client.

Return type *LXDInstance*

Returns LXD instance.

Raises

- **BaseConfigurationError** – on unexpected error configuration base.
- **LXDError** – on unexpected LXD error.

3.1.4 craft_providers.multipass package

Submodules

craft_providers.multipass.errors module

Multipass Errors.

```
exception craft_providers.multipass.errors.MultipassError(brief: str, details: Optional[str] = None,
                                                       resolution: Optional[str] = None)
```

Bases: *craft_providers.errors.ProviderError*

Unexpected Multipass error.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

```
exception craft_providers.multipass.errors.MultipassInstallationError(reason, *, details=None)
```

Bases: *craft_providers.multipass.errors.MultipassError*

Multipass Installation Error.

Parameters

- **reason** (str) – Reason for install failure.
- **details** (Optional[str]) – Optional details to include.

brief: str

craft_providers.multipass.installer module

Multipass Provider.

`craft_providers.multipass.installer.install()`

Install Multipass.

Return type str

Returns Multipass version.

Raises `MultipassInstallationError` – on error.

`craft_providers.multipass.installer.is_installed()`

Check if Multipass is installed (and found on PATH).

Return type bool

Returns True if multipass is installed.

craft_providers.multipass.multipass module

API provider for Multipass.

This implementation interfaces with multipass using the *multipass* command-line utility.

`class craft_providers.multipass.multipass.Multipass(*, multipass_path=PosixPath('multipass'))`

Bases: object

Wrapper for multipass command.

Parameters `multipass_path` (Path) – Path to multipass command to use.

Variables `minimum_required_version` – Minimum required version for compatibility.

`delete(*, instance_name, purge=True)`

Passthrough for running multipass delete.

Parameters

- `instance_name` (str) – The name of the instance_name to delete.
- `purge` – Flag to purge the instance_name’s image after deleting.

Raises `MultipassError` – on error.

Return type None

`exec(*, command, instance_name, runner=<function run>, **kwargs)`

Execute command in instance_name with specified runner.

Parameters

- `command` (List[str]) – Command to execute in the instance.
- `instance_name` (str) – Name of instance to execute in.
- `runner` (Callable) – Execution function to invoke, e.g. subprocess.run or Popen. First argument is finalized command with the attached kwargs.
- `kwargs` – Additional kwargs for runner.

Returns Runner’s instance.

`info(*, instance_name)`

Get information/state for instance.

Return type Dict[str, Any]

Returns Parsed json data from info command.

Raises `MultipassError` – On error.

Parameters `instance_name` (str) –

is_supported_version()

Check if Multipass version is supported.

A helper to check if Multipass meets minimum supported version for craft-providers.

Return type bool

Returns True if installed version is supported.

launch(*, instance_name, image, cpus=None, mem=None, disk=None)

Launch multipass VM.

Parameters

- `instance_name` (str) – The name the launched instance will have.
- `image` (str) – Name of image to create the instance with.
- `cpus` (Optional[str]) – Amount of virtual CPUs to assign to the launched instance.
- `mem` (Optional[str]) – Amount of RAM to assign to the launched instance.
- `disk` (Optional[str]) – Amount of disk space the launched instance will have.

Raises `MultipassError` – on error.

Return type None

list()

List names of VMs.

Return type List[str]

Returns Data from stdout if instance exists, else None.

Raises `MultipassError` – On error.

minimum_required_version = '1.7'

mount(*, source, target, uid_map=None, gid_map=None)

Mount host source path to target.

Parameters

- `source` (Path) – Path of local directory to mount.
- `target` (str) – Target mount points, in <name>[:<path>] format, where <name> is an instance name, and optional <path> is the mount point. If omitted, the mount point will be the same as the source's absolute path.
- `uid_map` (Optional[Dict[str, str]]) – A mapping of user IDs for use in the mount of the form <host-id> -> <instance-id>. File and folder ownership will be mapped from <host-id> to <instance-id> inside the instance.
- `gid_map` (Optional[Dict[str, str]]) – A mapping of group IDs for use in the mount of the form <host-id> -> <instance-id>. File and folder ownership will be mapped from <host-id> to <instance-id> inside the instance.

Return type None

start(*, instance_name)

Start VM instance.

Parameters **instance_name** (str) – the name of the instance to start.

Raises *MultipassError* – on error.

Return type None

stop(*, instance_name, delay_mins=0)

Stop VM instance.

Parameters

- **instance_name** (str) – the name of the instance_name to stop.

- **delay_mins** (int) – Delay shutdown for specified number of minutes.

Raises *MultipassError* – on error.

Return type None

transfer(*, source, destination)

Transfer to destination path with source IO.

Parameters

- **source** (str) – The source path, prefixed with <name:> for a path inside the instance.

- **destination** (str) – The destination path, prefixed with <name:> for a path inside the instance.

Raises *MultipassError* – On error.

Return type None

transfer_destination_io(*, source, destination, chunk_size=4096)

Transfer from source file to destination IO.

Note that this can't use std{in,out}=open(...) due to LP #1849753.

Parameters

- **source** (str) – The source path, prefixed with <name:> for a path inside the instance.

- **destination** (BufferedIOBase) – An IO stream to write to.

- **chunk_size** (int) – Number of bytes to transfer at a time. Defaults to 4096.

Raises *MultipassError* – On error.

Return type None

transfer_source_io(*, source, destination, chunk_size=4096)

Transfer to destination path with source IO.

Note that this can't use std{in,out}=open(...) due to LP #1849753.

Parameters

- **source** (BufferedIOBase) – An IO stream to read from.

- **destination** (str) – The destination path, prefixed with <name:> for a path inside the instance.

- **chunk_size** (int) – Number of bytes to transfer at a time. Defaults to 4096.

Raises *MultipassError* – On error.

Return type None

umount(**, mount*)

Unmount target in VM.

Parameters **mount** (str) – Mount point in <name>[:<path>] format, where <name> are instance names, and optional <path> are mount points. If omitted, all mounts will be removed from the named instance.

Raises *MultipassError* – On error.

Return type None

version()

Get multipass and multipassd versions.

Return type Tuple[str, Optional[str]]

Returns Tuple of parsed versions (multipass, multipassd). multipassd may be None if Multipass is not yet ready.

wait_until_ready(**, retry_wait=0.25, timeout=None*)

Wait until Multipass is ready (upon install/startup).

Parameters

- **retry_wait** (float) – Time to sleep between retries.
- **timeout** (Optional[float]) – Timeout in seconds.

Return type Tuple[str, Optional[str]]

Returns Tuple of parsed versions (multipass, multipassd). multipassd may be None if Multipass is not ready and the timeout limit is reached.

craft_providers.multipass.multipass_instance module

Multipass Instance.

class **craft_providers.multipass.multipass_instance.MultipassInstance**(**, name, multipass=None*
Bases: *craft_providers.executor.Executor*

Multipass Instance Lifecycle.

Parameters

- **name** (str) – Name of multipass instance.
- **multipass** (Optional[Multipass]) –

delete()

Delete instance and purge.

Return type None

execute_popen(command, *, cwd=None, env=None, **kwargs)

Execute process in instance using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.

- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments for subprocess.Popen().
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

execute_run(*command*, *, *cwd=None*, *env=None*, ***kwargs*)

Execute command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises `subprocess.CalledProcessError` – if command fails and check is True.

exists()

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises `MultipassError` – On unexpected failure.

is_mounted(*, *host_source*, *target*)

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (Path) – Instance path to check.

Return type bool

Returns True if host_source is mounted at target.

Raises `MultipassError` – On unexpected failure.

is_running()

Check if instance is running.

Return type bool

Returns True if instance is running.

Raises `MultipassError` – On unexpected failure.

launch(*, *image*, *cpus=2*, *disk_gb=256*, *mem_gb=2*)

Launch instance.

Parameters

- **image** (str) – Name of image to create the instance with.
- **instance_cpus** – Number of CPUs.
- **instance_disk_gb** – Disk allocation in gigabytes.
- **instance_mem_gb** – Memory allocation in gigabytes.
- **instance_name** – Name of instance to use/create.
- **instance_stop_time_mins** – Stop time delay in minutes.
- **cpus** (int) –
- **disk_gb** (int) –
- **mem_gb** (int) –

Raises *MultipassError* – On unexpected failure.

Return type None

mount(**, host_source, target*)

Mount host *host_source* directory to target mount point.

Checks first to see if already mounted.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (Path) – Instance path to mount to.

Raises *MultipassError* – On unexpected failure.

Return type None

pull_file(**, source, destination*)

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **MultipassError** – On unexpected error copying file.

Return type None

push_file(**, source, destination*)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **MultipassError** – On unexpected error copying file.

Return type None

push_file_io(**, destination, content, file_mode, group='root', user='root'*)

Create or replace file with content and file mode.

Multipass transfers data as “ubuntu” user, forcing us to first copy a file to a temporary location before moving to a (possibly) root-owned location and with appropriate permissions.

Parameters

- **destination** (Path) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Return type None

start()

Start instance.

Raises *MultipassError* – On unexpected failure.

Return type None

stop(**, delay_mins=0*)

Stop instance.

Parameters **delay_mins** (int) – Delay shutdown for specified minutes.

Raises *MultipassError* – On unexpected failure.

Return type None

umount(*target*)

Unmount mount target shared with host.

Parameters **target** (Path) – Target shared with host to umount.

Raises *MultipassError* – On failure to umount target.

Return type None

umount_all()

Unmount all mounts shared with host.

Raises *MultipassError* – On failure to umount target.

Return type None

Module contents

Multipass provider support package.

class `craft_providers.multipass.Multipass`(**, multipass_path=PosixPath('multipass')*)

Bases: object

Wrapper for multipass command.

Parameters **multipass_path** (Path) – Path to multipass command to use.

Variables **minimum_required_version** – Minimum required version for compatibility.

delete(**, instance_name*, *purge=True*)
Passthrough for running multipass delete.

Parameters

- **instance_name** (str) – The name of the instance_name to delete.
- **purge** – Flag to purge the instance_name’s image after deleting.

Raises *MultipassError* – on error.

Return type None

exec(**, command*, *instance_name*, *runner=<function run>*, ***kwargs*)
Execute command in instance_name with specified runner.

Parameters

- **command** (List[str]) – Command to execute in the instance.
- **instance_name** (str) – Name of instance to execute in.
- **runner** (Callable) – Execution function to invoke, e.g. subprocess.run or Popen. First argument is finalized command with the attached kwargs.
- **kwargs** – Additional kwargs for runner.

Returns Runner’s instance.

info(**, instance_name*)
Get information/state for instance.

Return type Dict[str, Any]

Returns Parsed json data from info command.

Raises *MultipassError* – On error.

Parameters **instance_name** (str) –

is_supported_version()
Check if Multipass version is supported.

A helper to check if Multipass meets minimum supported version for craft-providers.

Return type bool

Returns True if installed version is supported.

launch(**, instance_name*, *image*, *cpus=None*, *mem=None*, *disk=None*)
Launch multipass VM.

Parameters

- **instance_name** (str) – The name the launched instance will have.
- **image** (str) – Name of image to create the instance with.
- **cpus** (Optional[str]) – Amount of virtual CPUs to assign to the launched instance.
- **mem** (Optional[str]) – Amount of RAM to assign to the launched instance.
- **disk** (Optional[str]) – Amount of disk space the launched instance will have.

Raises *MultipassError* – on error.

Return type None

list()

List names of VMs.

Return type List[str]

Returns Data from stdout if instance exists, else None.

Raises MultipassError – On error.

minimum_required_version = '1.7'**mount(*, source, target, uid_map=None, gid_map=None)**

Mount host source path to target.

Parameters

- **source** (Path) – Path of local directory to mount.
- **target** (str) – Target mount points, in <name>[:<path>] format, where <name> is an instance name, and optional <path> is the mount point. If omitted, the mount point will be the same as the source’s absolute path.
- **uid_map** (Optional[Dict[str, str]]) – A mapping of user IDs for use in the mount of the form <host-id> -> <instance-id>. File and folder ownership will be mapped from <host-id> to <instance-id> inside the instance.
- **gid_map** (Optional[Dict[str, str]]) – A mapping of group IDs for use in the mount of the form <host-id> -> <instance-id>. File and folder ownership will be mapped from <host-id> to <instance-id> inside the instance.

Return type None

start(*, instance_name)

Start VM instance.

Parameters **instance_name** (str) – the name of the instance to start.

Raises MultipassError – on error.

Return type None

stop(*, instance_name, delay_mins=0)

Stop VM instance.

Parameters

- **instance_name** (str) – the name of the instance_name to stop.
- **delay_mins** (int) – Delay shutdown for specified number of minutes.

Raises MultipassError – on error.

Return type None

transfer(*, source, destination)

Transfer to destination path with source IO.

Parameters

- **source** (str) – The source path, prefixed with <name:> for a path inside the instance.
- **destination** (str) – The destination path, prefixed with <name:> for a path inside the instance.

Raises MultipassError – On error.

Return type None

`transfer_destination_io(*, source, destination, chunk_size=4096)`

Transfer from source file to destination IO.

Note that this can't use `std{in,out}=open(...)` due to LP #1849753.

Parameters

- **source** (str) – The source path, prefixed with <name:> for a path inside the instance.
- **destination** (BufferedIOBase) – An IO stream to write to.
- **chunk_size** (int) – Number of bytes to transfer at a time. Defaults to 4096.

Raises `MultipassError` – On error.

Return type None**`transfer_source_io(*, source, destination, chunk_size=4096)`**

Transfer to destination path with source IO.

Note that this can't use `std{in,out}=open(...)` due to LP #1849753.

Parameters

- **source** (BufferedIOBase) – An IO stream to read from.
- **destination** (str) – The destination path, prefixed with <name:> for a path inside the instance.
- **chunk_size** (int) – Number of bytes to transfer at a time. Defaults to 4096.

Raises `MultipassError` – On error.

Return type None**`umount(*, mount)`**

Unmount target in VM.

Parameters **mount** (str) – Mount point in <name>[:<path>] format, where <name> are instance names, and optional <path> are mount points. If omitted, all mounts will be removed from the named instance.

Raises `MultipassError` – On error.

Return type None**`version()`**

Get multipass and multipassd versions.

Return type Tuple[str, Optional[str]]

Returns Tuple of parsed versions (multipass, multipassd). multipassd may be None if Multipass is not yet ready.

`wait_until_ready(*, retry_wait=0.25, timeout=None)`

Wait until Multipass is ready (upon install/startup).

Parameters

- **retry_wait** (float) – Time to sleep between retries.
- **timeout** (Optional[float]) – Timeout in seconds.

Return type Tuple[str, Optional[str]]

Returns Tuple of parsed versions (multipass, multipassd). multipassd may be None if Multipass is not ready and the timeout limit is reached.

```
exception craft_providers.multipass.MultipassError(brief: str, details: Optional[str] = None,
                                                    resolution: Optional[str] = None)
```

Bases: *craft_providers.errors.ProviderError*

Unexpected Multipass error.

Parameters

- **brief** (str) –
- **details** (Optional[str]) –
- **resolution** (Optional[str]) –

brief: str

```
exception craft_providers.multipass.MultipassInstallationError(reason, *, details=None)
```

Bases: *craft_providers.multipass.errors.MultipassError*

Multipass Installation Error.

Parameters

- **reason** (str) – Reason for install failure.
- **details** (Optional[str]) – Optional details to include.

brief: str

```
class craft_providers.multipass.MultipassInstance(*, name, multipass=None)
```

Bases: *craft_providers.executor.Executor*

Multipass Instance Lifecycle.

Parameters

- **name** (str) – Name of multipass instance.
- **multipass** (Optional[Multipass]) –

delete()

Delete instance and purge.

Return type None

```
execute_popen(command, *, cwd=None, env=None, **kwargs)
```

Execute process in instance using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments for subprocess.Popen().
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

```
execute_run(command, *, cwd=None, env=None, **kwargs)
```

Execute command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises subprocess.CalledProcessError – if command fails and check is True.

exists()

Check if instance exists.

Return type bool

Returns True if instance exists.

Raises MultipassError – On unexpected failure.

is_mounted(*, host_source, target)

Check if path is mounted at target.

Parameters

- **host_source** (Path) – Host path to check.
- **target** (Path) – Instance path to check.

Return type bool

Returns True if host_source is mounted at target.

Raises MultipassError – On unexpected failure.

is_running()

Check if instance is running.

Return type bool

Returns True if instance is running.

Raises MultipassError – On unexpected failure.

launch(*, image, cpus=2, disk_gb=256, mem_gb=2)

Launch instance.

Parameters

- **image** (str) – Name of image to create the instance with.
- **instance_cpus** – Number of CPUs.
- **instance_disk_gb** – Disk allocation in gigabytes.
- **instance_mem_gb** – Memory allocation in gigabytes.
- **instance_name** – Name of instance to use/create.
- **instance_stop_time_mins** – Stop time delay in minutes.
- **cpus** (int) –

- **disk_gb** (int) –
- **mem_gb** (int) –

Raises *MultipassError* – On unexpected failure.

Return type None

mount(**, host_source, target*)

Mount host *host_source* directory to target mount point.

Checks first to see if already mounted.

Parameters

- **host_source** (Path) – Host path to mount.
- **target** (Path) – Instance path to mount to.

Raises *MultipassError* – On unexpected failure.

Return type None

pull_file(**, source, destination*)

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **MultipassError** – On unexpected error copying file.

Return type None

push_file(**, source, destination*)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **MultipassError** – On unexpected error copying file.

Return type None

push_file_io(**, destination, content, file_mode, group='root', user='root'*)

Create or replace file with content and file mode.

Multipass transfers data as “ubuntu” user, forcing us to first copy a file to a temporary location before moving to a (possibly) root-owned location and with appropriate permissions.

Parameters

- **destination** (Path) – Path to file.

- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File group owner/id.
- **user** (str) – File user owner/id.

Return type None

`start()`

Start instance.

Raises `MultipassError` – On unexpected failure.

Return type None

`stop(*, delay_mins=0)`

Stop instance.

Parameters `delay_mins` (int) – Delay shutdown for specified minutes.

Raises `MultipassError` – On unexpected failure.

Return type None

`umount(target)`

Unmount mount target shared with host.

Parameters `target` (Path) – Target shared with host to umount.

Raises `MultipassError` – On failure to umount target.

Return type None

`umount_all()`

Unmount all mounts shared with host.

Raises `MultipassError` – On failure to umount target.

Return type None

```
craft_providers.multipass.ensure_multipass_is_ready(*, multi-
pass=<craft_providers.multipass.multipass.Multipass
object>)
```

Ensure Multipass is ready for use.

Raises `MultipassError` – on error.

Parameters `multipass` (`Multipass`) –

Return type None

`craft_providers.multipass.install()`

Install Multipass.

Return type str

Returns Multipass version.

Raises `MultipassInstallationError` – on error.

`craft_providers.multipass.is_installed()`

Check if Multipass is installed (and found on PATH).

Return type bool

Returns True if multipass is installed.

```
craft_providers.multipass.launch(name, *, base_configuration, image_name, cpus=2, disk_gb=64,  
                                  mem_gb=2, auto_clean=False)
```

Create, start, and configure instance.

If auto_clean is enabled, automatically delete an existing instance that is deemed to be incompatible, rebuilding it with the specified environment.

Parameters

- **name** (str) – Name of instance.
- **base_configuration** ([Base](#)) – Base configuration to apply to instance.
- **image_name** (str) – Multipass image to use, e.g. snapcraft:core20.
- **cpus** (int) – Number of CPUs.
- **disk_gb** (int) – Disk allocation in gigabytes.
- **mem_gb** (int) – Memory allocation in gigabytes.
- **auto_clean** (bool) – Automatically clean instance, if incompatible.

Return type [MultipassInstance](#)

Returns Multipass instance.

Raises

- [BaseConfigurationError](#) – on unexpected error configuration base.
- [MultipassError](#) – on unexpected Multipass error.

3.1.5 craft_providers.util package

Submodules

craft_providers.util.env_cmd module

Helper(s) for env command.

```
craft_providers.util.env_cmd.formulate_command(env=None, *, chdir=None,  
                                               ignore_environment=False)
```

Create an env command with the specified environment.

For each key-value, the env command will include the key=value argument to the env command.

If a variable is None, then the env -u parameter will be used to unset it.

An empty environment will simply yield the env command.

NOTE: not all versions of *env* support –chdir, it is up to the caller to ensure compatibility.

Parameters

- **env** (Optional[Dict[str, Optional[str]]]) – Environment flags to set/unset.
- **chdir** (Optional[Path]) – Optional directory to run in.
- **ignore_environment** (bool) – Start with an empty environment.

Return type List[str]

Returns List of env command strings.

craft_providers.util.os_release module

Parser for /etc/os-release.

`craft_providers.util.os_release.parse_os_release(content)`

Parser for /etc/os-release.

Format documentation at:

<https://www.freedesktop.org/software/systemd/man/os-release.html>

Example os-release contents:

```
NAME="Ubuntu"
VERSION="20.10 (Groovy Gorilla)"
ID=ubuntu
ID_LIKE=debian
PRETTY_NAME="Ubuntu 20.10"
VERSION_ID="20.10"
HOME_URL="https://www.ubuntu.com/"
SUPPORT_URL="https://help.ubuntu.com/"
BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-policy"
VERSION_CODENAME=groovy
UBUNTU_CODENAME=groovy
```

Parameters `content` (str) – String contents of os-release file.

Return type Dict[str, str]

Returns Dictionary of key-mappings found in os-release. Values are stripped of encapsulating quotes.

craft_providers.util.snap_cmd module

Helper(s) for snap command.

`craft_providers.util.snap_cmd.formulate_local_install_command(classic, dangerous, snap_path)`

Formulate snap install command.

Parameters

- `classic` (bool) – Flag to enable installation of classic snap.
- `dangerous` (bool) – Flag to enable installation of snap without ack.
- `snap_path` (Path) –

Return type List[str]

Returns List of command parts.

`craft_providers.util.snap_cmd.formulate_refresh_command(snap_name, channel)`

Formulate snap refresh command.

Parameters

- `snap_name` (str) – The name of the channel.
- `channel` (str) – The channel to install the snap from.

Return type List[str]

Returns List of command parts.

`craft_providers.util.snap_cmd.formulate_remote_install_command(snap_name, channel, classic)`

Formulate the command to snap install from Store.

Parameters

- **snap_name** (str) – The name of the channel.
- **channel** (str) – The channel to install the snap from.
- **classic** (bool) – Flag to enable installation of classic snap.
- **dangerous** – Flag to enable installation of snap without ack.

Return type List[str]

Returns List of command parts.

`craft_providers.util.snap_cmd.formulate_remove_command(snap_name)`

Formulate snap remove command.

Parameters `snap_name` (str) – The name of the channel.

Return type List[str]

Returns List of command parts.

craft_providers.util.temp_paths module

Helpers for temporary files.

`craft_providers.util.temp_paths.home_temporary_directory()`

Create temporary directory in home directory where Multipass has access.

Return type Iterator[Path]

`craft_providers.util.temp_paths.home_temporary_file()`

Create a temporary directory in the home directory where Multipass has access.

Return type Iterator[Path]

Module contents

Utility modules.

3.2 Submodules

3.2.1 craft_providers.base module

Base configuration module.

`class craft_providers.base.Base`

Bases: abc.ABC

Interface for providers to configure instantiated environments.

Defines how to setup/configure an environment that has been instantiated by a provider and prepare it for some operation, e.g. execute build. It must account for:

- (1) the OS type and version.
- (2) the provided image that was launched, e.g. bootstrapping a minimal image versus a more fully featured one.
- (3) any dependencies that are required for the operation to complete, e.g. installed applications, networking configuration, etc. This includes any environment configuration that the application will assume is available.

Variables compatibility_tag – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: `compatibility_tag = f'{appname}-{Base.compatibility_tag}.{apprevision}'` to ensure base compatibility levels are maintained.

compatibility_tag: str = 'base-v0'

abstract get_command_environment()

Get command environment to use when executing commands.

Return type Dict[str, Optional[str]]

Returns Dictionary of environment, allowing None as a value to indicate that a value should be unset.

abstract setup(*, executor, retry_wait=0.25, timeout=None)

Prepare base instance for use by the application.

Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

Setup should not be called more than once in a given instance to refresh/update the environment, use `warmup` for that.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

abstract wait_until_ready(*, executor, retry_wait=0.25, timeout=None)

Wait until base instance is ready.

Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running `setup()`, e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.

- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

abstract `warmup(*, executor, retry_wait=0.25, timeout=None)`

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (`Executor`) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

3.2.2 `craft_providers.errors` module

Craft provider errors.

exception `craft_providers.errors.ProviderError(brief: str, details: Optional[str] = None, resolution: Optional[str] = None)`

Bases: `Exception`

Unexpected error.

Parameters

- **brief** (str) – Brief description of error.
- **details** (Optional[str]) – Detailed information.
- **resolution** (Optional[str]) – Recommendation, if any.

brief: str

details: Optional[str] = None

resolution: Optional[str] = None

`craft_providers.errors.details_from_called_process_error(error)`

Create a consistent ProviderError from command errors.

Parameters `error` (`CalledProcessError`) – `CalledProcessError`.

Return type str

Returns Details string.

`craft_providers.errors.details_from_command_error(*, cmd, returncode, stdout=None, stderr=None)`

Create a consistent ProviderError from command errors.

stdout and stderr, if provided, will be stringified using its object representation. This method does not decode byte strings.

Parameters

- **cmd** (`List[str]`) – Command executed.
- **returncode** (`int`) – Command exit code.
- **stdout** (`Union[str, bytes, None]`) – Optional stdout to include.
- **stderr** (`Union[str, bytes, None]`) – Optional stderr to include.

Return type `str`

Returns Details string.

3.2.3 `craft_providers.executor` module

Executor module.

`class craft_providers.executor.Executor`

Bases: `abc.ABC`

Interfaces to execute commands and move data in/out of an environment.

`abstract execute_popen(command, *, cwd=None, env=None, **kwargs)`

Execute a command in instance, using `subprocess.Popen()`.

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (`List[str]`) – Command to execute.
- **env** (`Optional[Dict[str, Optional[str]]]`) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (`Optional[Path]`) –

Return type `Popen`

Returns `Popen` instance.

`abstract execute_run(command, *, cwd=None, env=None, **kwargs)`

Execute a command using `subprocess.run()`.

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (`List[str]`) – Command to execute.
- **env** (`Optional[Dict[str, Optional[str]]]`) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to `subprocess.run()`.
- **cwd** (`Optional[Path]`) –

Return type `CompletedProcess`

Returns Completed process.

Raises `subprocess.CalledProcessError` – if command fails and check is True.

abstract `pull_file(*, source, destination)`

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (`destination.parent`) must exist.

Raises

- `FileNotFoundError` – If source file or destination's parent directory does not exist.
- `ProviderError` – On error copying file.

Return type None

abstract `push_file(*, source, destination)`

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (`destination.parent`) must exist.

Raises

- `FileNotFoundError` – If source file or destination's parent directory does not exist.
- `ProviderError` – On error copying file.

Return type None

abstract `push_file_io(*, destination, content, file_mode, group='root', user='root')`

Create or replace a file with specified content and file mode.

Parameters

- **destination** (Path) – Path to file.
- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File owner group.
- **user** (str) – File owner user.

Return type None

3.3 Module contents

Craft Providers base package.

class craft_providers.Base

Bases: abc.ABC

Interface for providers to configure instantiated environments.

Defines how to setup/configure an environment that has been instantiated by a provider and prepare it for some operation, e.g. execute build. It must account for:

- (1) the OS type and version.
- (2) the provided image that was launched, e.g. bootstrapping a minimal image versus a more fully featured one.
- (3) any dependencies that are required for the operation to complete, e.g. installed applications, networking configuration, etc. This includes any environment configuration that the application will assume is available.

Variables compatibility_tag – Tag/Version for variant of build configuration and setup. Any change to this version would indicate that prior [versioned] instances are incompatible and must be cleaned. As such, any new value should be unique to old values (e.g. incrementing). It is suggested to extend this tag, not overwrite it, e.g.: `compatibility_tag = f'{appname}-{Base.compatibility_tag}.{apprevision}'` to ensure base compatibility levels are maintained.

compatibility_tag: str = 'base-v0'

abstract get_command_environment()

Get command environment to use when executing commands.

Return type Dict[str, Optional[str]]

Returns Dictionary of environment, allowing None as a value to indicate that a value should be unset.

abstract setup(*, executor, retry_wait=0.25, timeout=None)

Prepare base instance for use by the application.

Wait for environment to become ready and configure it. At completion of setup, the executor environment should have networking up and have all of the installed dependencies required for subsequent use by the application.

Setup should not be called more than once in a given instance to refresh/update the environment, use `warmup` for that.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (`Executor`) – Executor for target container.
- **retry_wait** (`float`) – Duration to sleep() between status checks (if required).
- **timeout** (`Optional[float]`) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None

abstract `wait_until_ready(*, executor, retry_wait=0.25, timeout=None)`

Wait until base instance is ready.

Ensure minimum-required boot services are running. This would be used when starting an environment's container/VM after already [recently] running setup(), e.g. rebooting the instance. Allows the environment to be used without the cost incurred by re-executing the steps unnecessarily.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None**abstract** `warmup(*, executor, retry_wait=0.25, timeout=None)`

Prepare a previously created and setup instance for use by the application.

Ensure the instance is still valid and wait for environment to become ready.

If timeout is specified, abort operation if time has been exceeded.

Parameters

- **executor** (*Executor*) – Executor for target container.
- **retry_wait** (float) – Duration to sleep() between status checks (if required).
- **timeout** (Optional[float]) – Timeout in seconds.

Raises

- **BaseCompatibilityError** – if instance is incompatible.
- **BaseConfigurationError** – on other unexpected error.

Return type None**class** `craft_providers.Executor`

Bases: abc.ABC

Interfaces to execute commands and move data in/out of an environment.

abstract `execute_popen(command, *, cwd=None, env=None, **kwargs)`

Execute a command in instance, using subprocess.Popen().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Additional keyword arguments to pass.
- **cwd** (Optional[Path]) –

Return type Popen

Returns Popen instance.

abstract execute_run(*command*, *, *cwd=None*, *env=None*, ***kwargs*)

Execute a command using subprocess.run().

The process' environment will inherit the execution environment's default environment (PATH, etc.), but can be additionally configured via env parameter.

Parameters

- **command** (List[str]) – Command to execute.
- **env** (Optional[Dict[str, Optional[str]]]) – Additional environment to set for process.
- **kwargs** – Keyword args to pass to subprocess.run().
- **cwd** (Optional[Path]) –

Return type CompletedProcess

Returns Completed process.

Raises subprocess.CalledProcessError – if command fails and check is True.

abstract pull_file(*, *source*, *destination*)

Copy a file from the environment to host.

Parameters

- **source** (Path) – Environment file to copy.
- **destination** (Path) – Host file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **ProviderError** – On error copying file.

Return type None

abstract push_file(*, *source*, *destination*)

Copy a file from the host into the environment.

Parameters

- **source** (Path) – Host file to copy.
- **destination** (Path) – Target environment file path to copy to. Parent directory (*destination.parent*) must exist.

Raises

- **FileNotFoundException** – If source file or destination's parent directory does not exist.
- **ProviderError** – On error copying file.

Return type None

abstract push_file_io(*, *destination*, *content*, *file_mode*, *group='root'*, *user='root'*)

Create or replace a file with specified content and file mode.

Parameters

- **destination** (Path) – Path to file.

- **content** (BytesIO) – Contents of file.
- **file_mode** (str) – File mode string (e.g. ‘0644’).
- **group** (str) – File owner group.
- **user** (str) – File owner user.

Return type None

```
exception craft_providers.ProviderError(brief: str, details: Optional[str] = None, resolution: Optional[str] = None)
```

Bases: Exception

Unexpected error.

Parameters

- **brief** (str) – Brief description of error.
- **details** (Optional[str]) – Detailed information.
- **resolution** (Optional[str]) – Recommendation, if any.

brief: str

details: Optional[str] = None

resolution: Optional[str] = None

**CHAPTER
FOUR**

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

C

craft_providers, 77
craft_providers.actions, 20
craft_providers.actions.snap_installer, 19
craft_providers.base, 72
craft_providers.bases, 25
craft_providers.bases.buildd, 20
craft_providers.bases.errors, 23
craft_providers.bases.instance_config, 23
craft_providers.errors, 74
craft_providers.executor, 75
craft_providers.lxd, 42
craft_providers.lxd.errors, 28
craft_providers.lxd.installer, 28
craft_providers.lxd.launcher, 29
craft_providers.lxd.lxc, 30
craft_providers.lxd.lxd, 37
craft_providers.lxd.lxd_instance, 38
craft_providers.lxd.project, 41
craft_providers.lxd.remotes, 42
craft_providers.multipass, 62
craft_providers.multipass.errors, 55
craft_providers.multipass.installer, 56
craft_providers.multipass.multipass, 56
craft_providers.multipass.multipass_instance,
 59
craft_providers.util, 72
craft_providers.util.env_cmd, 70
craft_providers.util.os_release, 71
craft_providers.util.snap_cmd, 71
craft_providers.util.temp_paths, 72

INDEX

A

alias (*craft_providers.bases.buildd.BuilddBBase attribute*), 20

B

Base (*class in craft_providers*), 13, 77

Base (*class in craft_providers.base*), 72

BaseCompatibilityError, 23, 25

BaseConfigurationError, 23, 25

BIONIC (*craft_providers.bases.buildd.BuilddBBaseAlias attribute*), 22

BIONIC (*craft_providers.bases.BuilddBBaseAlias attribute*), 27

brief (*craft_providers.actions.snap_installer.SnapInstallationError attribute*), 19

brief (*craft_providers.bases.BaseCompatibilityError attribute*), 25

brief (*craft_providers.bases.BaseConfigurationError attribute*), 25

brief (*craft_providers.bases.errors.BaseCompatibilityError attribute*), 23

brief (*craft_providers.bases.errors.BaseConfigurationError attribute*), 23

brief (*craft_providers.errors.ProviderError attribute*), 74

brief (*craft_providers.lxd.errors.LXDLError attribute*), 28

brief (*craft_providers.lxd.errors.LXDInstallationError attribute*), 28

brief (*craft_providers.lxd.LXDLError attribute*), 49

brief (*craft_providers.lxd.LXDInstallationError attribute*), 50

brief (*craft_providers.multipass.errors.MultipassError attribute*), 55

brief (*craft_providers.multipass.errors.MultipassInstallationError attribute*), 55

brief (*craft_providers.multipass.MultipassError attribute*), 66

brief (*craft_providers.multipass.MultipassInstallationError attribute*), 66

brief (*craft_providers.ProviderError attribute*), 80

BuilddBBase (*class in craft_providers.bases*), 15, 25

BuilddBBase (*class in craft_providers.bases.buildd*), 20

BuilddBBaseAlias (*class in craft_providers.bases*), 27

BuilddBBaseAlias (*class in craft_providers.bases.buildd*), 22

C

compatibility_tag (*craft_providers.Base attribute*), 77

compatibility_tag (*craft_providers.base.Base attribute*), 73

compatibility_tag (*craft_providers.bases.buildd.BuilddBBase attribute*), 20

compatibility_tag (*craft_providers.bases.BuilddBBase compatibility_tag attribute*), 26

compatibility_tag (*craft_providers.bases.instance_config.InstanceConfig attribute*), 23

config_device_add_disk() (*craft_providers.lxd.LXC method*), 42

config_device_add_disk()

(*craft_providers.lxd.lxc.LXC method*), 30

config_device_remove() (*craft_providers.lxd.LXC method*), 42

config_device_remove()

(*craft_providers.lxd.lxc.LXC method*), 30

config_device_show() (*craft_providers.lxd.LXC method*), 43

config_device_show() (*craft_providers.lxd.lxc.LXC method*), 31

config_set() (*craft_providers.lxd.LXC method*), 43

config_set() (*craft_providers.lxd.lxc.LXC method*), 31

configure_buildb_image_remote() (*in module craft_providers.lxd*), 53

configure_buildb_image_remote() (*in module craft_providers.lxd.remotes*), 42

craft_providers

module, 77

craft_providers.actions

module, 20

craft_providers.actions.snap_installer

module, 19

craft_providers.base

module, 72

```

craft_providers.bases
    module, 25
craft_providers.bases.buildd
    module, 20
craft_providers.bases.errors
    module, 23
craft_providers.bases.instance_config
    module, 23
craft_providers.errors
    module, 74
craft_providers.executor
    module, 75
craft_providers.lxd
    module, 42
craft_providers.lxd.errors
    module, 28
craft_providers.lxd.installer
    module, 28
craft_providers.lxd.launcher
    module, 29
craft_providers.lxd.lxc
    module, 30
craft_providers.lxd.lxd
    module, 37
craft_providers.lxd.lxd_instance
    module, 38
craft_providers.lxd.project
    module, 41
craft_providers.lxd.remotes
    module, 42
craft_providers.multipass
    module, 62
craft_providers.multipass.errors
    module, 55
craft_providers.multipass.installer
    module, 56
craft_providers.multipass.multipass
    module, 56
craft_providers.multipass.multipass_instance
    module, 59
craft_providers.util
    module, 72
craft_providers.util.env_cmd
    module, 70
craft_providers.util.os_release
    module, 71
craft_providers.util.snap_cmd
    module, 71
craft_providers.util.temp_paths
    module, 72
create_with_default_profile() (in     module
    craft_providers.lxd.project), 41

```

D

```

default_command_environment() (in     module
    craft_providers.bases.buildd), 22
delete() (craft_providers.lxd.LXC method), 43
delete() (craft_providers.lxd.lxc.LXC method), 31
delete() (craft_providers.lxd.lxd_instance.LXDInstance
    method), 38
delete() (craft_providers.lxd.LXDInstance method), 5,
    50
delete() (craft_providers.multipass.Multipass method),
    62
delete() (craft_providers.multipass.multipass.Multipass
    method), 56
delete() (craft_providers.multipass.multipass_instance.MultipassInstance
    method), 59
delete() (craft_providers.multipass.MultipassInstance
    method), 8, 66
details (craft_providers.errors.ProviderError     at-
    tribute), 74
details (craft_providers.ProviderError attribute), 80
details_from_called_process_error() (in module
    craft_providers.errors), 74
details_from_command_error() (in     module
    craft_providers.errors), 74

```

E

```

ensure_lxd_is_ready() (in     module
    craft_providers.lxd), 53
ensure_lxd_is_ready() (in     module
    craft_providers.lxd.installer), 28
ensure_multipass_is_ready() (in     module
    craft_providers.multipass), 69
exec() (craft_providers.lxd.LXC method), 43
exec() (craft_providers.lxd.lxc.LXC method), 31
exec() (craft_providers.multipass.Multipass method),
    63
exec() (craft_providers.multipass.multipass.Multipass
    method), 56
execute_popen() (craft_providers.Executor method),
    3, 78
execute_popen() (craft_providers.executor.Executor
    method), 75
execute_popen() (craft_providers.lxd.lxd_instance.LXDInstance
    method), 38
execute_popen() (craft_providers.lxd.LXDInstance
    method), 5, 50
execute_popen() (craft_providers.multipass.multipass_instance.Multipas
    method), 59
execute_popen() (craft_providers.multipass.MultipassInstance
    method), 8, 66
execute_run() (craft_providers.Executor method), 3,
    79
execute_run() (craft_providers.executor.Executor
    method), 75

```

```

execute_run() (craft_providers.lxd.lxd_instance.LXDInstance)
    home_temporary_directory() (in module
        craft_providers.util.temp_paths), 72
execute_run() (craft_providers.lxd.LXDInstance)
    home_temporary_file() (in module
        craft_providers.util.temp_paths), 72
execute_run() (craft_providers.multipass.multipass_instance.MultipassInstance)
    |
image_copy() (craft_providers.lxd.LXC method), 45
image_copy() (craft_providers.lxd.lxc.LXC method), 33
image_delete() (craft_providers.lxd.LXC method), 45
image_delete() (craft_providers.lxd.lxc.LXC method),
    33
image_list() (craft_providers.lxd.LXC method), 45
image_list() (craft_providers.lxd.lxc.LXC method), 33
info() (craft_providers.lxd.LXC method), 45
INFO() (craft_providers.lxd.lxc.LXC method), 33
info() (craft_providers.multipass.Multipass method),
    63
info() (craft_providers.multipass.multipass.Multipass
method), 56
init() (craft_providers.lxd.LXD method), 49
init() (craft_providers.lxd.lxd.LXD method), 37
inject_from_host() (in module
    craft_providers.actions.snap_installer), 19
install() (in module craft_providers.lxd), 53
install() (in module craft_providers.lxd.installer), 28
install() (in module craft_providers.multipass), 69
install() (in module
    craft_providers.multipass.installer), 56
install_from_store() (in module
    craft_providers.actions.snap_installer), 19
instance_config_class
    (craft_providers.bases.builddd.BuilddBase
attribute), 21
instance_config_class
    (craft_providers.bases.BuilddBase attribute),
    15, 26
instance_config_path
    (craft_providers.bases.builddd.BuilddBase
attribute), 21
instance_config_path
    (craft_providers.bases.BuilddBase attribute),
    26
InstanceConfiguration (class
    in
        craft_providers.bases.instance_config), 23
is_initialized() (in module craft_providers.lxd), 54
is_initialized() (in module
    craft_providers.lxd.installer), 29
is_installed() (in module craft_providers.lxd), 54
is_installed() (in module
    craft_providers.lxd.installer), 29
is_installed() (in module craft_providers.multipass),
    69
is_installed() (in module
    craft_providers.multipass.installer), 56

```

F

```

file_pull() (craft_providers.lxd.LXC method), 44
file_pull() (craft_providers.lxd.lxc.LXC method), 32
file_push() (craft_providers.lxd.LXC method), 44
file_push() (craft_providers.lxd.lxc.LXC method), 32
FOCAL (craft_providers.bases.builddd.BuilddBaseAlias
attribute), 22
FOCAL (craft_providers.bases.BuilddBaseAlias attribute),
    27
formulate_command() (in module
    craft_providers.util.env_cmd), 70
formulate_local_install_command() (in module
    craft_providers.util.snap_cmd), 71
formulate_refresh_command() (in module
    craft_providers.util.snap_cmd), 71
formulate_remote_install_command() (in module
    craft_providers.util.snap_cmd), 72
formulate_remove_command() (in module
    craft_providers.util.snap_cmd), 72

```

G

```

get_command_environment() (craft_providers.Base
method), 13, 77
get_command_environment() (craft_providers.base.Base method), 73
get_command_environment() (craft_providers.bases.builddd.BuilddBase
method), 21
get_command_environment() (craft_providers.bases.BuilddBase
method), 15, 26

```

H

```

has_image() (craft_providers.lxd.LXC method), 44
has_image() (craft_providers.lxd.lxc.LXC method), 33

```

i

- is_mounted() (*craft_providers.lxd.lxd_instance.LXDInstance* method), 39
- is_mounted() (*craft_providers.lxd.LXDInstance* method), 5, 51
- is_mounted() (*craft_providers.multipass.multipass_instance.MultipassInstance* method), 60
- is_mounted() (*craft_providers.multipass.MultipassInstance* method), 9, 67
- is_running() (*craft_providers.lxd.lxd_instance.LXDInstance* method), 39
- is_running() (*craft_providers.lxd.LXDInstance* method), 6, 51
- is_running() (*craft_providers.multipass.multipass_instance.MultipassInstance* method), 60
- is_running() (*craft_providers.multipass.MultipassInstance* method), 9, 67
- is_supported_version() (*craft_providers.lxd.LXD* method), 49
- is_supported_version() (*craft_providers.lxd.lxd.LXD* method), 37
- is_supported_version() (*craft_providers.multipass.Multipass* method), 63
- is_supported_version() (*craft_providers.multipass.multipass.Multipass* method), 57
- is_user_permitted() (*in module craft_providers.lxd*), 54
- is_user_permitted() (*in module craft_providers.lxd.installer*), 29

J

- JAMMY (*craft_providers.bases.buildd.BuilddBaseAlias* attribute), 22
- JAMMY (*craft_providers.bases.BuilddBaseAlias* attribute), 27

L

- launch() (*craft_providers.lxd.LXC* method), 46
- launch() (*craft_providers.lxd.lxc.LXC* method), 34
- launch() (*craft_providers.lxd.lxd_instance.LXDInstance* method), 39
- launch() (*craft_providers.lxd.LXDInstance* method), 6, 51
- launch() (*craft_providers.multipass.Multipass* method), 63
- launch() (*craft_providers.multipass.multipass.Multipass* method), 57
- launch() (*craft_providers.multipass.multipass_instance.MultipassInstance* method), 60
- launch() (*craft_providers.multipass.MultipassInstance* method), 9, 67
- launch() (*in module craft_providers.lxd*), 54
- launch() (*in module craft_providers.lxd.launcher*), 29

M

- marshal() (*craft_providers.bases.instance_config.InstanceConfiguration* method), 24
- minimum_required_version (*craft_providers.lxd.LXD* attribute), 49
- minimum_required_version (*craft_providers.lxd.lxd.LXD* attribute), 37
- minimum_required_version (*craft_providers.multipass.Multipass* attribute), 64
- minimum_required_version (*craft_providers.multipass.multipass.Multipass* attribute), 57
- module
 - craft_providers, 77
 - craft_providers.actions, 20
 - craft_providers.actions.snap_installer, 19
 - craft_providers.base, 72
 - craft_providers.bases, 25
 - craft_providers.bases.buildd, 20
 - craft_providers.bases.errors, 23
 - craft_providers.bases.instance_config, 23
 - craft_providers.errors, 74
 - craft_providers.executor, 75
 - craft_providers.lxd, 42
 - craft_providers.lxd.errors, 28
 - craft_providers.lxd.installer, 28
 - craft_providers.lxd.launcher, 29
 - craft_providers.lxd.lxc, 30
 - craft_providers.lxd.lxd, 37
 - craft_providers.lxd.lxd_instance, 38

craft_providers.lxd.project, 41
 craft_providers.lxd.remotes, 42
 craft_providers.multipass, 62
 craft_providers.multipass.errors, 55
 craft_providers.multipass.installer, 56
 craft_providers.multipass.multipass, 56
 craft_providers.multipass.multipass_instance, 59
 craft_providers.util, 72
 craft_providers.util.env_cmd, 70
 craft_providers.util.os_release, 71
 craft_providers.util.snap_cmd, 71
 craft_providers.util.temp_paths, 72
 mount() (*craft_providers.lxd.lxd_instance.LXDInstance method*), 39
 mount() (*craft_providers.lxd.LXDInstance method*), 6, 51
 mount() (*craft_providers.multipass.Multipass method*), 64
 mount() (*craft_providers.multipass.multipass.Multipass method*), 57
 mount() (*craft_providers.multipass.multipass_instance.MultipassInstance method*), 61
 mount() (*craft_providers.multipass.MultipassInstance method*), 9, 68
 Multipass (*class in craft_providers.multipass*), 62
 Multipass (*class in craft_providers.multipass.multipass*), 56
 MultipassError, 55, 65
 MultipassInstallationError, 55, 66
 MultipassInstance (*class in craft_providers.multipass*), 8, 66
 MultipassInstance (*class in craft_providers.multipass.multipass_instance*), 59

P

parse_os_release() (*in module craft_providers.util.os_release*), 71
 profile_edit() (*craft_providers.lxd.LXC method*), 46
 profile_edit() (*craft_providers.lxd.lxc.LXC method*), 34
 profile_show() (*craft_providers.lxd.LXC method*), 47
 profile_show() (*craft_providers.lxd.lxc.LXC method*), 35
 project_create() (*craft_providers.lxd.LXC method*), 47
 project_create() (*craft_providers.lxd.lxc.LXC method*), 35
 project_delete() (*craft_providers.lxd.LXC method*), 47
 project_delete() (*craft_providers.lxd.lxc.LXC method*), 35
 project_list() (*craft_providers.lxd.LXC method*), 47

project_list() (*craft_providers.lxd.lxc.LXC method*), 35
 ProviderError, 74, 80
 publish() (*craft_providers.lxd.LXC method*), 47
 publish() (*craft_providers.lxd.lxc.LXC method*), 35
 pull_file() (*craft_providers.Executor method*), 3, 79
 pull_file() (*craft_providers.executor.Executor method*), 76
 pull_file() (*craft_providers.lxd.lxd_instance.LXDInstance method*), 40
 pull_file() (*craft_providers.lxd.LXDInstance method*), 6, 52
 pull_file() (*craft_providers.multipass.multipass_instance.MultipassInstance method*), 61
 pull_file() (*craft_providers.multipass.MultipassInstance method*), 10, 68
 purge() (*in module craft_providers.lxd.project*), 41
 push_file() (*craft_providers.Executor method*), 4, 79
 push_file() (*craft_providers.executor.Executor method*), 76
 push_file() (*craft_providers.lxd.lxd_instance.LXDInstance method*), 40
 push_file() (*craft_providers.lxd.LXDInstance method*), 7, 52
 push_file() (*craft_providers.multipass.multipass_instance.MultipassInstance method*), 61
 push_file() (*craft_providers.multipass.MultipassInstance method*), 10, 68
 push_file_io() (*craft_providers.Executor method*), 4, 79
 push_file_io() (*craft_providers.executor.Executor method*), 76
 push_file_io() (*craft_providers.lxd.lxd_instance.LXDInstance method*), 40
 push_file_io() (*craft_providers.lxd.LXDInstance method*), 7, 52
 push_file_io() (*craft_providers.multipass.multipass_instance.MultipassInstance method*), 62
 push_file_io() (*craft_providers.multipass.MultipassInstance method*), 10, 68

R

remote_add() (*craft_providers.lxd.LXC method*), 48
 remote_add() (*craft_providers.lxd.lxc.LXC method*), 36
 remote_list() (*craft_providers.lxd.LXC method*), 48
 remote_list() (*craft_providers.lxd.lxc.LXC method*), 36
 resolution (*craft_providers.errors.ProviderError attribute*), 74
 resolution (*craft_providers.ProviderError attribute*), 80

S

save() (*craft_providers.bases.instance_config.InstanceConfiguration*)

```

        method), 24
setup() (craft_providers.Base method), 13, 77
setup() (craft_providers.base.Base method), 73
setup() (craft_providers.bases.buildd.BuilddBase
        method), 21
setup() (craft_providers.bases.BuilddBase method), 15,
        26
SnapInstallationError, 19
snaps (craft_providers.bases.instance_config.InstanceConfigura-
        tion attribute), 24
start() (craft_providers.lxd.LXC method), 48
start() (craft_providers.lxd.lxc.LXC method), 36
start() (craft_providers.lxd.lxd_instance.LXDInstance
        method), 40
start() (craft_providers.lxd.LXDInstance method), 7,
        52
start() (craft_providers.multipass.Multipass method),
        64
start() (craft_providers.multipass.multipass.Multipass
        method), 57
start() (craft_providers.multipass.multipass_instance.MultipassIn-
        stance method), 62
start() (craft_providers.multipass.MultipassInstance
        method), 10, 69
stop() (craft_providers.lxd.LXC method), 48
stop() (craft_providers.lxd.lxc.LXC method), 36
stop() (craft_providers.lxd.lxd_instance.LXDInstance
        method), 40
stop() (craft_providers.lxd.LXDInstance method), 7, 53
stop() (craft_providers.multipass.Multipass method),
        64
stop() (craft_providers.multipass.multipass.Multipass
        method), 58
stop() (craft_providers.multipass.multipass_instance.MultipassIn-
        stance method), 62
stop() (craft_providers.multipass.MultipassInstance
        method), 11, 69
supports_mount() (craft_providers.lxd.lxd_instance.LXDInstan-
        ce method), 41
supports_mount() (craft_providers.lxd.LXDInstance
        method), 7, 53

```

T

```

transfer() (craft_providers.multipass.Multipass
        method), 64
transfer() (craft_providers.multipass.multipass.Multipass
        method), 58
transfer_destination_io()
        (craft_providers.multipass.Multipass method),
        64
transfer_destination_io()
        (craft_providers.multipass.multipass.Multipass
        method), 58

```

U

```

transfer_source_io()
        (craft_providers.multipass.Multipass method),
        65
transfer_source_io()
        (craft_providers.multipass.multipass.Multipass
        method), 58

```

V

```

mount() (craft_providers.multipass.Multipass method),
        65
umount() (craft_providers.multipass.multipass.Multipass
        method), 59
unmarshal() (craft_providers.bases.instance_config.InstanceConfigura-
        tion class method), 24
unmount() (craft_providers.lxd.lxd_instance.LXDInstance
        method), 41
unmount() (craft_providers.lxd.LXDInstance method),
        7, 53
unmount() (craft_providers.multipass.multipass_instance.MultipassIn-
        stance method), 62
umount() (craft_providers.multipass.MultipassInstance
        method), 11, 69
unmount_all() (craft_providers.lxd.lxd_instance.LXDInstance
        method), 41
unmount_all() (craft_providers.lxd.LXDInstance
        method), 8, 53
unmount_all() (craft_providers.multipass.multipass_instance.MultipassIn-
        stance method), 62
unmount_all() (craft_providers.multipass.MultipassInstance
        method), 11, 69
update() (craft_providers.bases.instance_config.InstanceConfigura-
        tion class method), 24
update_nested_dictionaries() (in module
        craft_providers.bases.instance_config), 24

```

W

```

version() (craft_providers.lxd.LXD method), 49
version() (craft_providers.lxd.lxd.LXD method), 37
version() (craft_providers.multipass.Multipass
        method), 65
version() (craft_providers.multipass.multipass.Multipass
        method), 59

```

`wait_until_ready()` (*craft_providers.multipass.Multipass method*), 65
`wait_until_ready()` (*craft_providers.multipass.multipass.Multipass method*), 59
`warmup()` (*craft_providers.Base method*), 14, 78
`warmup()` (*craft_providers.base.Base method*), 74
`warmup()` (*craft_providers.bases.buildd.BuilddBase method*), 22
`warmup()` (*craft_providers.bases.BuilddBase method*), 16, 27

X

`XENIAL` (*craft_providers.bases.buildd.BuilddBaseAlias attribute*), 22
`XENIAL` (*craft_providers.bases.BuilddBaseAlias attribute*), 27